

RSA NetWitness Logs

Event Source Log Configuration Guide



RSA Authentication Manager Express

Last Modified: Friday, January 20, 2017

Event Source Product Information:

Vendor: [RSA, The Security Division of EMC](#)

Event Source: Authentication Manager Express

Versions: 1.0

RSA Product Information:

Supported On: NetWitness Suite 10.0 and later

Event Source Log Parser: rsaacesrv

Collection Method: Syslog

Event Source Class.Subclass: Security.Access Control

To configure the RSA Authentication Manager Express event source, you must:

- I. [Configure RSA Authentication Manager Express](#)
- II. [Configure NetWitness Suite](#)

Configure RSA Authentication Manager Express

After you install RSA Authentication Manager Express, perform the following actions to set up RSA Authentication Manager Express to communicate with RSA NetWitness Suite.

To configure RSA Authentication Manager to send Syslog messages to RSA NetWitness Suite:

1. Log onto the RSA Security Console.
2. Click **Setup > System Settings**.
3. From the **Network & Communication Settings** section, click **Log Configuration**.
4. In the **Log Data Destination** section, set the parameters as follows:
 - To send Admin audit events to RSA NetWitness Suite, enter the IP address of the RSA NetWitness Log Decoder or Remote Log Collector in the **Administrative Audit Log Data** field.
 - To send Runtime audit events to RSA NetWitness Suite, enter the IP address of the RSA NetWitness Log Decoder or Remote Log Collector in the **Runtime Audit Log Data** field.
 - To send System audit events to audit events to RSA NetWitness Suite, enter the IP address of the RSA NetWitness Log Decoder or Remote Log Collector in the **System Log Data** field.

Note: For these fields, ensure that you select the **Save to internal database and remote SysLog at the following hostname or IP address** radio button, or else the RSA NetWitness Suite IP address is not active.

5. Click **Save**.

Configure NetWitness Suite

Perform the following steps in RSA NetWitness Suite:

- Ensure the required parser is enabled
- Configure Syslog Collection

Ensure the Required Parser is Enabled

If you do not see your parser in the list while performing this procedure, you need to download it in RSA NetWitness Suite Live Services.

Ensure that the parser for your event source is enabled:

1. In the **NetWitness** menu, select **Administration > Services**.
2. In the Services grid, select a Log Decoder, and from the Actions menu, choose **View > Config**.
3. In the Service Parsers Configuration panel, search for your event source, and ensure that the **Config Value** field for your event source is selected.

Note: The required parser is `rsaacesrv`.



Configure Syslog Collection

Note: You only need to configure Syslog collection the first time that you set up an event source that uses Syslog to send its output to NetWitness.

You should configure either the Log Decoder or the Remote Log Collector for Syslog. You do not need to configure both.

To configure the Log Decoder for Syslog collection:

1. In the **NetWitness** menu, select **Administration > Services**.
2. In the Services grid, select a Log Decoder, and from the Actions menu, choose **View > System**.
3. Depending on the icon you see, do one of the following:

- If you see  **Start Capture**, click the icon to start capturing Syslog.
- If you see  **Stop Capture**, you do not need to do anything; this Log Decoder is already capturing Syslog.

To configure the Remote Log Collector for Syslog collection:

1. In the **NetWitness** menu, select **Administration > Services**.
2. In the Services grid, select a Remote Log Collector, and from the Actions menu, choose **View > Config > Event Sources**.
3. Select **Syslog/Config** from the drop-down menu.

The Event Categories panel displays the Syslog event sources that are configured, if any.
4. In the Event Categories panel toolbar, click **+**.

The Available Event Source Types dialog is displayed.
5. Select either **syslog-tcp** or **syslog-udp**. You can set up either or both, depending on the needs of your organization.
6. Select the new type in the Event Categories panel and click **+** in the Sources panel toolbar.

The Add Source dialog is displayed.
7. Enter **514** for the port, and select **Enabled**. Optionally, configure any of the Advanced parameters as necessary.

Click **OK** to accept your changes and close the dialog box.

Once you configure one or both syslog types, the Log Decoder or Remote Log Collector collects those types of messages from all available event sources. So, you can continue to add Syslog event sources to your system without needing to do any further configuration in NetWitness.

Copyright © 2017 EMC Corporation. All Rights Reserved.

Trademarks

RSA, the RSA Logo and EMC are either registered trademarks or trademarks of EMC Corporation in the United States and/or other countries. All other trademarks used herein are the property of their respective owners.