



Hosts and Services Getting Started Guide

for Version 11.2



Copyright © 1994-2019 Dell Inc. or its subsidiaries. All Rights Reserved.

Contact Information

RSA Link at <https://community.rsa.com> contains a knowledgebase that answers common questions and provides solutions to known problems, product documentation, community discussions, and case management.

Trademarks

For a list of RSA trademarks, go to www.emc.com/legal/emc-corporation-trademarks.htm#rsa.

License Agreement

This software and the associated documentation are proprietary and confidential to Dell, are furnished under license, and may be used and copied only in accordance with the terms of such license and with the inclusion of the copyright notice below. This software and the documentation, and any copies thereof, may not be provided or otherwise made available to any other person.

No title to or ownership of the software or documentation or any intellectual property rights thereto is hereby transferred. Any unauthorized use or reproduction of this software and the documentation may be subject to civil and/or criminal liability.

This software is subject to change without notice and should not be construed as a commitment by Dell.

Third-Party Licenses

This product may include software developed by parties other than RSA. The text of the license agreements applicable to third-party software in this product may be viewed on the product documentation page on RSA Link. By using this product, a user of this product agrees to be fully bound by terms of the license agreements.

Note on Encryption Technologies

This product may contain encryption technology. Many countries prohibit or restrict the use, import, or export of encryption technologies, and current use, import, and export regulations should be followed when using, importing or exporting this product.

Distribution

Dell believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

January 2019

Contents

Hosts and Services Basics	9
What Is a Host	9
What Is a Host Type	9
What Is a Service	10
Setting Up a Host	11
Maintaining Hosts	12
Update Version Naming Convention	12
Maintaining Services	13
Services Implemented with the NetWitness Server	13
Running in Mixed Mode	14
Functionality Gaps Encountered During in Staggered Updates	14
Examples of Staggered Updates	15
Example 2. Multiple Decoders and Concentrators, Alternative 2	15
Example 3. Multiple Regions	16
Hosts and Services Procedures	17
Step 1. Deploy a Host	19
Step 2. Install a Service on a Host	20
Step 3. Review SSL Ports for Trusted Connections	21
Encrypted SSL Ports	21
Step 4. Manage Access to a Service	23
Test a Trusted Connection	23
Apply Version Updates to a Host	26
Apply Updates from the Hosts View (Web Access)	26
Task 1. Populate Local Repo or Set Up an External Repo	26
Task 2. Apply Updates from the Hosts View to Each Host	26
Apply Updates from the Command Line (No Web Access)	28
Populate Local Update Repository	29
Set Up an External Repository with RSA and OS Updates	31
Create and Manage Host Groups	34
Create a Group	34
Change the Name of a Group	35
Add a Host to a Group	35
View the Hosts in a Group	35
Remove a Host from a Group	35
Delete a Group	36
Search for Hosts	36

Search for a Host	36
Find the Host that Runs a Service	37
Execute a Task From the Host Task List	37
Add and Delete a Filesystem Monitor	39
Configure the Filesystem Monitor	40
Delete a Filesystem Monitor	40
Reboot a Host	41
Shut Down and Restart a Host from the Hosts View	41
Shut Down and Restart a Host from the Host Task List	42
Set Host Built-In Clock	42
Set the Time on the Local Clock	42
Set Network Configuration	43
Specify the Network Address for a Host	43
Set Network Time Source	44
Specify the Network Clock Source	44
Set SNMP	45
Toggle SNMP Service on the Host	45
Set Syslog Forwarding	46
Set Up and Start Syslog Forwarding	47
Show Network Port Status	48
Display the Network Port Status	48
Show Serial Number	49
Show the Serial Number	49
Shut Down Host	49
Shut Down the Host	50
Stop and Start a Service on a Host	50
Stop a Service on a Host	50
Start a Service on a Host	51
Add, Replicate, or Delete a Service User	52
Procedures	52
Add a Service User Role	55
Procedure	56
Change a Service User Password	57
Create and Manage Service Groups	58
Create a Group	59
Change the Name of a Group	60
Add a Service to a Group	60
View the Services in a Group	60
Remove a Service from a Group	60
Delete a Group	61

Duplicate or Replicate a Service Role	61
Duplicate a Service Role	62
Replicate a Role	62
Edit Core Service Configuration Files	62
Edit a Service Configuration File	63
Revert to a Backup Version of a Service Configuration File	64
Push a Configuration File to Other Services	64
Edit or Delete a Service	72
Procedures	73
Explore and Edit Service Property Tree	74
Terminate a Connection to a Service	75
Terminate a Session on a Service	76
Terminate an Active Query in a Session	76
Search for Services	77
Search for a Service	77
Filter Services by Type	78
Find the Services on a Host	80
Start, Stop, or Restart a Service	80
Start a Service	80
Stop a Service	81
Restart a Service	81
View Service Details	81
Purpose of Each Service View	81
Access a Service View	82
Hosts and Services Views References	84
Hosts View	85
Workflow	86
What do you want to do?	86
Quick Look	87
Hosts Panel Toolbar	87
Groups Panel Toolbar	88
Services View	90
Workflow	91
What do you want to do?	91
Related Topic	92
Quick Look	92
Edit Service Dialog	95
Groups Panel Toolbar	97
Services Panel Toolbar	98
Services Config View	99

Topic	103
Features	104
Edit a Service Configuration File	106
Files Tab Toolbar	106
Services Explore View	108
The Node List	109
The Monitor Panel	110
Features	112
Services Logs View	113
Services Security View	115
Roles and Service Access	116
Features	118
Role Name Panel	118
Role Information and Permissions Panel	119
Service User Roles	120
Service User Permissions	120
Features	124
SDK Meta Role Permissions Options	124
Features	126
User List Panel	126
User Definition Panel	128
Services Stats View	131
Summary Stats Section	132
Gauges	135
Timelines	135
Historical Timelines	135
Chart Stats Tray	135
Components	137
Features	138
System View	140
Services Info Toolbar	141
Features	143
Host Task Selection List	144
Service Configuration Settings	146
Appliance Service Configuration Parameters	146
Archiver Service Configuration View	146
Broker Service Configuration Parameters	148

Aggregation Configuration Parameters	149
Concentrator Service Configuration Parameters	150
Core Service Logging Configuration Parameters	151
Core Service-to-Service Configuration Parameters	152
Core Service System Configuration Parameters	153
Decoder Service Configuration Parameters	154
Decoder and Log Decoder Configuration Parameters	154
Log Decoder Service Configuration Parameters	157
REST Interface Configuration Parameters	160
NetWitness Platform Core Service system.roles Modes	160
Troubleshooting Version Installations and Updates	162
Update for Host fails	162
Update for Service Fails	163
Update for Host Download Error	164
deploy_admin Password Expired	165

Hosts and Services Basics

This guide gives administrators the standard procedures for add and configure hosts and services in NetWitness Platform. After introducing you to the basic purpose of hosts and services and how they function within in the NetWitness Platform network, this guide covers:

- Tasks you must complete to set up hosts and services in your network
- Additional procedures that you complete based on the long-term and daily, operational needs of your enterprise
- Reference topics that describe the user interface


Go to the [Master Table of Contents](#) to find all NetWitness Platform Logs & Network 11.x documents.

What Is a Host

A host is the machine on which a service runs and can be a physical or virtual machine. See the "NetWitness Platform Detailed Host Deployment Diagram" in the *NetWitness Platform Deployment Guide* for an illustration of how host are deployed.

What Is a Host Type

A host type assigns a service or services to a host when you install a host from the Hosts view. You choose a **Host Type** in the **Install Services** dialog which is displayed when you select a host in the

Hosts view and click . The following table lists each host type and the services it installs. See the "NetWitness Platform Detailed Host Deployment Diagram" in the *NetWitness Platform Deployment Guide* for an illustration of how host are deployed.

Host Type	Services Installed
Archiver	Workbench and Archiver
Broker	Broker
Cloud Gateway	Cloud Gateway
Concentrator	Concentrator
Endpoint Hybrid	Log Decoder, Endpoint, and Concentrator
Endpoint Log Hybrid	Log Collector, Log Decoder, Endpoint, and Concentrator
ESA Primary	Context Hub, Entity Behavior Analysis, and Event Stream Analysis
ESA Secondary	Event Stream Analysis, and Entity Behavior Analysis
Log Collector	Log Collector

Host Type	Services Installed
Log Decoder	Log Collector and Log Decoder
Log Hybrid	Log Collector, Log Decoder, and Concentrator
Malware Analysis	Malware Analysis and Broker
Network Decoder	Decoder (Packets)
Network Hybrid	Concentrator and Decoder
UEBA	UEBA
Warehouse Connector	Warehouse Connector

What Is a Service

A service performs a unique function, such as collecting logs or archiving data. Each service runs on a dedicated port and is modeled as a plug-in to enable or disable, according to the function of the host.

You must configure the following core services first:


- Decoder
- Concentrator
- Broker
- Log Decoder

All the services are listed below and each service except the Log Collector has its own guide or shares a guide in the *Host and Services Configuration Guides*. The Log Collector has its own set of configuration guides to handle the configuration for all the supported event collection protocols. For Log Collector information, see *Log Collection Guides*.

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Admin	N/A	N/A	Implemented with the NW Server
Archiver	50008	56008	
Broker	50003	56003	Core Service
Cloud Gateway	N/A	N/A	
Concentrator	50005	56005	Core Service
Config	N/A	N/A	Implemented with the NW Server.
Content	N/A	N/A	Implemented with the NW Server
Context Hub	N/A	N/A	

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Decoder (Packets)	50004	56004	Core Service
Endpoint	N/A	N/A	
Entity Behavior Analysis	N/A	N/A	
Event Stream Analysis	N/A	50030	
Integration	N/A	N/A	Implemented with the NW Server.
Investigate	N/A	N/A	Implemented with the NW Server.
Log Collector	50001	56001	
Log Decoder	50002	56002	Core Service
Malware Analysis	N/A	60007	
Orchestration	N/A	N/A	Implemented with the NW Server.
Reporting Engine	N/A	51113	Implemented with the NW Server.
Respond	N/A	N/A	Implemented with the NW Server.
Security	N/A	N/A	Implemented with the NW Server.
Source	N/A	N/A	Implemented with the NW Server
UEBA	N/A	N/A	
Warehouse Connector	50020	56020	
Workbench	50007	56007	

You must configure hosts and services to communicate with the network and each other so they can perform their functions such as storing or capturing data.



Setting Up a Host

You use the Hosts view to add a host to NetWitness Platform. See [Step 1. Deploy a Host](#) for detailed instructions.

Maintaining Hosts

You use the main ADMIN > Hosts view to add, edit, delete, and perform other maintenance tasks for the hosts in your deployment. You use the Task List dialog to perform tasks relating to a host and its communications with the network. See [Hosts and Services Procedures](#) for detailed instructions.

After initial implementation of NetWitness Platform, the major task you perform from the Hosts view is updating your NetWitness Platform deployment to a new version.

Update Version Naming Convention

You use the Hosts view to apply the latest version updates from your [Populate Local Update Repository](#). You must understand the update version naming convention to know which version you want to apply to the host. The naming convention is *major-release.minor-release.service-pack.patch*. For example, if you choose 11.6.1.2, you apply the following version to the host.

- 11 = major release
- 6 = minor release
- 1 = service pack
- 2 = patch

NetWitness Platform supports multiple versions in your deployment. The NetWitness Server (NW Server Host) is updated first and all other hosts must have the same or earlier version as the NW Server Host.

The following example is a single version deployment with all hosts updated to 11.2.0.0 (latest RSA release available).

The screenshot shows the NetWitness Platform interface with the 'ADMIN' tab selected. The 'Hosts' sub-tab is active, displaying a table of hosts. The table has columns for Name, Host, Services, Current Version, Update Version, and Status. All hosts are listed as 'Up-to-Date' with version 11.2.0.0. The 'Services' column shows various components like NW Server, Archiver, Concentrator, etc., each with a green status indicator and a number.

Name	Host	Services	Current Version	Update Version	Status
☐ NW Server (co-located Broker)	IP-address	12	11.2.0.0	11.2.0.0	Up-to-Date
☐ Archiver	IP-address	2	11.2.0.0	11.2.0.0	Up-to-Date
☐ Concentrator	IP-address	1	11.2.0.0	11.2.0.0	Up-to-Date
☐ Endpoint Log Hybrid	IP-address	4	11.2.0.0	11.2.0.0	Up-to-Date
☐ Event Stream Analysis Primary	IP-address	4	11.2.0.0	11.2.0.0	Up-to-Date
☐ Log Decoder	IP-address	2	11.2.0.0	11.2.0.0	Up-to-Date
☐ Log Hybrid	IP-address	3	11.2.0.0	11.2.0.0	Up-to-Date
☐ Malware Analysis	IP-address	2	11.2.0.0	11.2.0.0	Up-to-Date
☐ Network Decoder (Packets)	IP-address	1	11.2.0.0	11.2.0.0	Up-to-Date
☐ Network Hybrid (Packets)	IP-address	2	11.2.0.0	11.2.0.0	Up-to-Date

Maintaining Services

You use the ADMIN > Services view to add, edit, delete, monitor, and perform other maintenance tasks for the services in your deployment. See [Hosts and Services Procedures](#) for detailed instructions.

Services Implemented with the NetWitness Server

The services in the following table are implemented when you deploy the NW Server to support:

- the expansion of physical and virtual deployment platforms and improvements to host and service maintenance.
- Content, Investigate, Respond, and Source functionality.

Caution: You do not need to configure these services to deploy NetWitness Platform. RSA recommends that you monitor the operating status of these services using Health-and-Wellness. Do not attempt to modify the parameters in the Explore view without contacting Customer Support (<https://community.rsa.com/docs/DOC-1294>).

Service	Purpose
Admin	The Administration Server (Admin server) is the back-end service for administrative tasks in the NetWitness Platform User Interface (UI). It abstracts authentication, global preferences management, and authorization support for the UI. The Admin server requires the Config server and the Security server to be online to perform its role.
Config	The Configuration Server (Config server) stores and manages configuration sets. A configuration set is any logical configuration group that is managed independently. The Config server facilitates the sharing of properties among services, provides configuration backup and restore facilities, and tracks changes to properties.
Content	The Content server manages the RSA provided and user created parser rules. For more information on parser management search for "parsers" in RSA Link.
Integration	The Integration Server manages interactions with external systems. The service handles the following outbound or inbound channels. • REST API Gateway - gateway to external REST clients that assigns calls to the NetWitness Application Programming Interface (API). • Notifications Dispatcher - centralized dispatcher for all outbound notifications originating in the NetWitness deployment.
Investigate	The Investigate server supports Investigate and Malware Analysis functionality. For more information see the <i>NetWitness Platform Investigate and Malware Analysis User Guide</i> .
Orchestration	The Orchestration server provisions, installs, and configures all services in your NetWitness Platform deployment.

Service	Purpose
Respond	The Respond server supports Respond functionality. For more information see the <i>NetWitness Platform Respond Configuration Guide</i> .
Security	The NetWitness Platform Security Server (Security server) manages the security infrastructure of a NetWitness Platform deployment. It handles the following security-related concerns. • Users and the authentication accounts • Role Based Access Control (RBAC) • Deployment PKI infrastructure A NetWitness Platform deployment has users with authentication accounts. Independent of how you verify the identity of the analyst (for example, Active Directory), NetWitness Platform must maintain user state that is not provided by all authentication providers (for example, last login time, failed login attempts, and roles). The concept of a user is separate from the identity associated with the user and the Security server maintains these as separate User and Account entities. In addition to the out-of-the-box local NetWitness accounts available to all NetWitness deployments, the server supports external authentication providers. The Security server also implements RBAC by managing Role and Permission entities. Permissions can be assigned to roles and roles to users. Together these enable a flexible authorization policy for the deployment. The server also manages generation of cryptographically secure tokens that encode the applicable authorization for a user. These tokens form the basis for deployment wide authorization.
Source	The Source server is reserved for future use and will provide a centralized location to configure sources (for example, Endpoints and Log Sources).

Running in Mixed Mode

Mixed mode occurs when some services are updated to the latest version and some are still on older versions. This happens when you update the hosts in your deployment to the latest version in phases (or stagger the update).

Functionality Gaps Encountered During in Staggered Updates

If you stagger the update, you:

- May not have all the features operational until you update your entire deployment.
- Will not have service administrative features available until you update all the hosts in your deployment.
- May be without data capture for a period of time.

Examples of Staggered Updates

In the following examples, all the hosts are on 11.2.0.x and you want to stagger the host updates to version 11.2.1.0.

Example 1. Multiple Decoders and Concentrators, Alternative 1

In this example, the 11.2.0.x deployment includes one NW Server host, two Decoder hosts, two Concentrator hosts, one Archiver host, one Broker host, one Event Stream Analysis host, and one Malware Analysis host.

You must complete Phase 1 first and update the hosts in the order listed for Phase 1.

RSA recommends that you update the Phase 2 hosts in the order listed for Phase 1

Phase 1 - session 1

1. Update the NetWitness Server host.
2. Update the Event Stream Analysis host.
3. Update the Malware Analysis host.
4. Update the Broker or Concentrator host.

Phase 2 - session 2

1. Update 2 Decoder hosts.
2. Update 2 Concentrator hosts and Archiver host.

Phase 2 - session 3

1. Update all other hosts.

Example 2. Multiple Decoders and Concentrators, Alternative 2

In this example, the 11.2.0.x deployment includes one NW Server host, two Decoder hosts, two Concentrator hosts, one Broker host, one Event Stream Analysis host, and one Malware Analysis host. RSA recommends that you update the Phase 2 hosts the following sequence (you must complete Phase 1 first and update the hosts in the order listed).

Phase 1 - session 1

1. Update the NetWitness Server host.
2. Update the Event Stream Analysis host.
3. Update the Malware Analysis host.
4. Update the Broker host.

Phase 2 - session 2

1. Update one Decoder host and one Concentrator host.
Time elapses during which NetWitness Platform processes a significant amount of data.

Phase 2 - session 3

1. Update one Decoder host, one Concentrator host, and the Broker host.
2. Update all Log Decoder hosts before you update Virtual Log Collectors.
3. Update all other hosts.

Example 3. Multiple Regions

In this example, the 11.2.0.x deployment includes one NW Server host, one Event Stream Analysis host, one Malware Analysis host, four Decoder hosts, four Concentrator hosts, two Broker hosts, (two sites, each with two Decoders, two Concentrators, and one Broker).

Phase 1 - Update Site 1


1. Update the NW Server host.
2. Update the Event Stream Analysis host.
3. Update the Malware Analysis host.
4. Update one Broker host, two Decoder hosts, and two Concentrator hosts.
5. Update all the other hosts.

Phase 2 - Update Site 2

1. Update the Broker hosts.
2. Update two Decoder hosts.
3. Update two Concentrator hosts.
4. Update all the other hosts.

Hosts and Services Procedures

Every service requires a host. After you set up a host, you can assign services to and from this host to other hosts in your NetWitness Platform deployment.



High-Level Task	Description
Set Up a Host	Complete the following tasks in the order shown to set up a host. Step 1. Deploy a host Step 2. Install a service on a host Step 3. Review SSL Ports for Trusted Connections Step 4. Manage access to a service

High-Level Task	Description
Maintain a Host - Basics	The following maintenance tasks are shown in alphabetical order. • Apply version updates to a host. • Populate Local Update Repository • Set Up an External Repository with RSA and OS Updates • Create and manage host groups • Search for hosts • Set network configuration • Set network time source • Show network port status • Show serial number • Shut down a host • Stop and start a service on a host
Maintain a Host from the Host Task List Dialog	You use the Host Task List dialog to manage tasks that relate to a host and its communications with the network. Several service and host configuration options are available for core hosts. • Execute a task from the Host Task List • Add and delete a Filesystem monitor • Reboot a host • Set host built-in clock • Set network configuration. • Set network time source • Set SNMP • Set Syslog forwarding • Show network port status • Show serial number • Shut down host • Stop and start a service on a host

High-Level Task	Description
Maintain a Service	The following procedures describe how to maintain services. • Add, replicate or delete a service user • Add a service user role • Change a service user password • Create and manage service groups • Duplicate or replicate a service role • Edit core service configuration files • Edit or delete a service • Explore and edit service property tree • Terminate a connection to a service • Search for services • Start, stop or restart a service • View service details

Step 1. Deploy a Host

Caution: If you include "." in a host name, the host name must also include a valid domain name.

1. Deploy a host.

You can deploy a physical host (RSA Appliance), virtual host on-prem, a virtual in AWS, or a virtual host in Azure. See the following guides for instructions on how to deploy hosts.

- *[RSA NetWitness® Platform Physical Host Deployment Guide](#)*
- *[RSA NetWitness® Platform Virtual Host Deployment Guide](#)*
- *[RSA NetWitness® Platform AWS Deployment Guide](#)*
- *[RSA NetWitness® Platform Azure Deployment Guide](#)*


2. Go to **Administration > Hosts**.

The **New Hosts** dialog is displayed with the hosts that you deployed.

3. Select the hosts that you want to enable.

The **Enable** menu option becomes active.

4. Click **Enable**.



5. Select the host you enabled.

The host is displayed in the Hosts view. At this point, you can install a service on the host.


Step 2. Install a Service on a Host

Perform the following steps to install a service on a host.

1. In NetWitness Platform, go to **ADMIN > Hosts**.

The **Hosts** view is displayed.

2. Select the host on which you want to install the service (for example, **Event Stream Analysis**).


3. Click  in the toolbar.

The **Install Services** dialog is displayed.

4. Select a service from the **Host Type** drop-down list (for example, **ESA Primary**).

The  becomes active in the **Install Services** dialog.

5. Click **Install**.



Step 3. Review SSL Ports for Trusted Connections

To support trusted connections each core service has two ports, an unencrypted non-SSL port and an encrypted SSL port. Trusted connections require the encrypted SSL port.

Encrypted SSL Ports

When you install or upgrade to 10.4 or later, trusted connections are established by default with two settings:

- SSL is enabled.
- Core service is connected to an encrypted SSL port.

Each NetWitness Platform Core service has two ports:

- Unencrypted **non-SSL port**
Example: Archiver 50008

- **Encrypted SSL port**

Example: Archiver 56008

The SSL port is the non-SSL port + 6000.

The following table lists all NetWitness Platform services with their respective ports and shows that each core service has two ports. All port numbers listed are TCP.

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Admin	N/A	N/A	Implemented with the NW Server
Archiver	50008	56008	
Broker	50003	56003	Core Service
Cloud Gateway	N/A	N/A	
Concentrator	50005	56005	Core Service
Config	N/A	N/A	Implemented with the NW Server.
Content	N/A	N/A	Implemented with the NW Server
Context Hub	N/A	N/A	
Decoder (Packets)	50004	56004	Core Service
Endpoint	N/A	N/A	
Entity Behavior Analysis	N/A	N/A	
Event Stream Analysis	N/A	50030	
Integration	N/A	N/A	Implemented with the NW Server.
Investigate	N/A	N/A	Implemented with the NW Server.
Log Collector	50001	56001	
Log Decoder	50002	56002	Core Service
Malware Analysis	N/A	60007	
Orchestration	N/A	N/A	Implemented with the NW Server.
Reporting Engine	N/A	51113	Implemented with the NW Server.
Respond	N/A	N/A	Implemented with the NW Server.
Security	N/A	N/A	Implemented with the NW Server.
Source	N/A	N/A	Implemented with the NW Server
UEBA	N/A	N/A	

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Warehouse Connector	50020	56020	
Workbench	50007	56007	

Step 4. Manage Access to a Service

In a trusted connection, a service explicitly trusts the NW Server to manage and authenticate users. With this trust, services in **ADMIN > Services** no longer require credentials to be defined for every NetWitness Platform Core service. Instead, users who have been authenticated by the server can access the service without entering another password.

Test a Trusted Connection

Prerequisites

1. A role must be assigned to the user.
For more information see **Add a User and Assign a Role** topic in the *System Security and User Management Guide*.
2. The user must:
 - Log in to NetWitness Platform for the server to authenticate the user.
 - Have access to the service.

Procedure

1. In NetWitness Platform, go to **ADMIN > Services**.
The Services view is displayed.

RSA RESPOND INVESTIGATE MONITOR CONFIGURE ADMIN

Hosts Services Event Sources Health & Wellness System Security


Groups

Services

Name	License	Host	Type	Version	Actions
Admin	✓	NW Server	Admin Server	11.2.0.0	
Archiver	✓	Archiver	Archiver	11.2.0.0	
Broker	✓	Broker	Broker	11.2.0.0	
Cloud Gateway	✓	Cloud Gateway	Cloud Gateway Serve	11.2.0.0	
Concentrator	✓	Concentrator	Concentrator	11.2.0.0	
Config	✓	NW Server	Config Server	11.2.0.0	
Content	✓	NW Server	Content Server	11.2.0.0	
Context Hub	✓	Event Stream Ana	Contexthub Server	11.2.0.0	
Decoder	✓	Decoder	Decoder	1.2.0.0	
Endpoint	✓	Endpoint Hybrid	Endpoint	11.2.0.0	
Entity Behavior Analysis	✓	Event Stream Ana	Entity Behavior Ana	11.2.0.0	
Event Stream Analysis	✓	Event Stream Ana	Event Stream Analys	11.2.0.0	
Integration	✓	NW Server	Integration Serv	11.2.0.0	
Investigate	✓	NW Server	Investigate Server	11.2.0.0	
Log Collector	✓	Log Decoder	Log Collector	11.2.0.0	
Log Decoder	✓	Log Decoder	Log Decoder	11.2.0.0	
Log Decoder	✓	Endpoint Hybrid	Log Decoder	11.2.0.0	
Malware Analysis	✓	Malware Analysis	Malware Analys	11.2.0.0	
Orchestration	✓	NW Server	Orchestration Serve	11.2.0.0	
Reporting Engine	✓	NW Server	Reporting Engine	11.2.0.0	
Respond	✓	NW Server	Respond Server	11.2.0.0	
Security	✓	NW Server	Security Server	11.2.0.0	
Source	✓	NW Server	Source Server	11.2.0.0	
UEBA	✓	UEBA	UEBA	11.2.0.0	
Workbench	✓	Archiver	Workbench	11.2.0.0	

RSA NETWITNESS PLATFORM 11.2.0.0

2. Select the service (for example, a Concentrator) to test and click . The **Edit Service** dialog is displayed.




The **Edit Service** dialog box is shown. It has a title bar with a question mark and a close button. The main area contains the following fields:

- Service**: Concentrator
- Host**: Concentrator
- Name**: Concentrator
- Connection Details** (grouped box):
 - Port**: 56005
 - SSL**: ☒

At the bottom of the main area is a **Test Connection** button. At the bottom of the dialog are **Cancel** and **Save** buttons.

3. Remove the **Username** to test the connection without credentials.
4. Click **Test Connection**.



The **Edit Service** dialog box is shown again, identical to the previous one, but with an additional message at the bottom of the main area: **Test connection successful**. The **Test Connection** button is still present.

The message **Test connection successful** confirms the trusted connection is established.

The previously authenticated user can access the service without typing a username and password on the service.

5. Click **Save**.

Apply Version Updates to a Host

Complete the following tasks to update a host to a new version update.

Use the following methods to apply version updates to a host.

Note: If you have changed your location of the repository, see [Set Up an External Repository with RSA and OS Updates](#) for instructions.

- [Apply updates from the Host view \(Web Access\)](#)
- [Apply update from the command line \(No Web Access\)](#)

Apply Updates from the Hosts View (Web Access)

Task 1. Populate Local Repo or Set Up an External Repo

When you set up your NW Server, you select the Local Repository (Repo) or an External Repository (Repo). The Hosts view retrieves version updates from the repo you selected.

If you select the Local Repo, you do not need to set it up, but you must make sure that it is populated with the latest version updates. See [Populate Local Repository](#) for instructions on how to populate it with a version update.

Note: If you selected an External Repo, you must set it up. For more information on how for instructions on how to populate it with a version update see [Set Up an External Repository with RSA and OS Updates](#).


Task 2. Apply Updates from the Hosts View to Each Host

The Hosts view displays the software version updates available in your Local Update Repository and you choose and apply the updates you want from the Host view.

This procedure tells you how to update a host to a new version of NetWitness Platform.

Note: This topic uses NetWitness Platform 11.0.x.x to 11.1.0.0 as an example.

1. Log in to NetWitness Platform.
2. Go to **ADMIN > HOSTS**.
3. (Conditional) Check for the latest updates.




4. Select a host or hosts.

You must update the NW Server to the latest version first. You can update the other hosts in any sequence you prefer, but RSA recommends that you follow the guidelines in [Running in Mixed Mode](#).


Update Available is displayed in the **Status** column if you have an version update in your Local Update Repository for the selected hosts.

5. Select the version you want to apply from the **Update Version** column.




If you:


- Want to update more than one host to that version, after you update the NW Server host, select the checkbox to the left of the hosts. Only currently supported update versions are listed.
- Want to view a dialog with the major features in the update, click the  to the right of the update version number. The following is an example of this dialog.



- Cannot find the version you want, select **Update > Check for Updates** to check the repository for any available updates. If an update is available, the message "New updates are available" is displayed, and the **Status** column updates automatically to show **Update Available**. By default, only supported updates for the selected host are displayed.
6. Click **Update > Update Host** from the toolbar.



A dialog is displayed with information on the selected update. Click **Begin Update**.



The **Status** column tells you what is happening in each of the following stages of the update:

- Stage 1 - **Downloading update packages** - downloads the repository artifacts to the NW Server applicable to the services on the host you chose.
 - Stage 2 - **Configuring update packages** - configures update files in to correct format.
 - Stage 3 - **Update in progress** - updates host to the new version.
7. When you see **Update in progress**, refresh the browser.
- This may display the NetWitness Log In screen from which you log in again and navigate back to the Host view.
- After the host is updated, NetWitness Platform prompts you to **Reboot Host**.
8. Click **Reboot Host** from the toolbar.
- NetWitness Platform shows the status as **Rebooting...** until the host comes back online and the **Status** shows **Up-to-Date**. Contact Customer Care if the host does not come back online.

Note: If you have the Defense Information Systems Agency Security Technical Implementation Guide (DISA STIG) enabled, opening core services can take approximately 5 to 10 minutes. This delay is caused by the generation of new certificates.

Apply Updates from the Command Line (No Web Access)

If your NetWitness Platform deployment does not have Web access, complete the following procedure to apply a version update.

Note: In the following procedure, 11.1.0.0 is the version update used as an example in the code strings.

1. Download .zip update package for the version you want (for example, `netwitness-11.1.0.0.zip`) from RSA Link to a local directory.
2. SSH to the NW Server host.
3. Make a `/tmp/upgrade/<version>` staging directory for the version you want (for example, `tmp/upgrade/11.1.0.0`).
`mkdir -p /tmp/upgrade/11.1.0.0`


4. Copy the .zip update package a directory on the to the NW Server other than the staging directory (for example /tmp directory).
5. Unzip the package into the staging directory you created (for example, /tmp/upgrade/11.1.0.0)
.
`unzip /<download-location>/netwitness-11.1.0.0.zip -d /tmp/upgrade/11.1.0.0`
6. Initialize the update on the NW Server.
`upgrade-cli-client --init --version 11.1.0.0 --stage-dir /tmp/upgrade/`
7. Apply the update to the NW Server.
`upgrade-cli-client --upgrade --host-addr <NW Server IP> --version 11.1.0.0`
8. Log in to NetWitness Platform and reboot the NW Server host in the Host View.
9. Apply update to each non-NW Server host.
`upgrade-cli-client --upgrade --host-addr <non-NW Server IP address> --version 11.1.0.0`
The update is complete when the polling is completed.
10. Log in to NetWitness Platform and reboot the host in the Host View.
You can verify the version applied to the host with the following command:
`upgrade-cli-client --list`

Populate Local Update Repository

NetWitness Platform sends version updates to the Local Update Repository from the Live Update Repository. Access to the Live Update Repository requires and uses the Live Account credentials configured under **ADMIN > SYSTEM > Live**. In addition, you must check the **Automatically download information about new updates every day** checkbox under **ADMIN > SYSTEM > Updates** to populate the Local Repo daily.

The following diagram illustrates how you obtain version updates if your NetWitness Platform deployment has Web Access.

RSA NetWitness Platform® 11.x.x.x Version Update Workflow – Web Access



Note: When you make the initial connection with the Live Update Repository, you will be accessing all the CentOS 7 system packages and the RSA Production packages. This download of over 2.5 GB of data takes an indeterminate amount of time depending on your NW Server Internet connection and the traffic of the RSA Repository. It is not mandatory to use the Live Update Repository. Alternatively you can use an External Repo as described in [Set Up an External Repository with RSA and OS Updates](#).


To connect to the Live Update Repository, go to the ADMIN > System view, select **Live Services** in the options panel and make sure that credentials are configured (**Connection** light should be green). If it is not green, click **Sign In** and connect.

Note: If you need to use proxy to reach out to the Live Update Repository, you can configure the Proxy Host, Proxy Username, and Proxy Password. For more information see "Configure Proxy for NetWitness Platform" in the *NetWitness Platform 1.1 System Configuration Guide*.

See [Apply Updates from the Command Line \(No Web Access\)](#) if your NetWitness Platform deployment does not have Web Access.

The following diagram illustrates how you obtain version updates if your NetWitness Platform deployment does not have Web Access.

RSA NetWitness Platform® 11.x.x.x Version Update Workflow – No Web Access



Set Up an External Repository with RSA and OS Updates

Note: In the following procedure, 11.1.0.0 is the version update used as an example in the code strings.

Complete the following procedure to set up an external repository (Repo).

Note: 1.) You need an unzip utility installed on the host to complete this procedure. 2.) You must know how to create a web server before you complete the following procedure.

1. (Conditional) Complete this step if you have an external repo and you want to override it.
 - Case 1: You bootstrapped the host from an external repo and you want to upgrade using a local repo on the Admin Server.
 - a. Create the `/etc/netwitness/platform/repobase` file.


```
vi /etc/netwitness/platform/netwitness/repobase
```
 - b. Edit the `repobase` file so that the only information in the file is the following URL.

```
https://nw-node-zero/nwrpmrepo
```

- c. Complete the instructions on how to run the upgrade using the `upgrade-cli-client` tool.
- Case 2: You bootstrapped the host from local repo on the Admin server (NW Server host) and you want to use an external repo for the upgrade.
 - a. Create the `/etc/netwitness/platform/repobase` file.

```
vi /etc/netwitness/platform/netwitness/repobase
```
 - b. Edit the `repobase` file so that the only information in the file is the following URL.

```
https://<webserver-ip>/<alias-for-repo>
```
 - c. Complete the instructions on how to run the upgrade using the `upgrade-cli-client` tool. The instructions are in the [Apply Updates from the Command Line \(No Web Access\)](#).

2. Set up the external repo.

- a. Log in to the web server host
- b. Create directory to host the NW repository (`netwitness-11.2.0.0.zip`), for example `ziprepo` under `web-root` of the web server. For example, `/var/netwitness` is the `web-root`, run the following command string.

```
mkdir -p /var/netwitness/<your-zip-file-repo>
```
- c. Create the `11.2.0.0` directory under `/var/netwitness/<your-zip-file-repo>`.

```
mkdir -p /var/netwitness/<your-zip-file-repo>/11.2.0.0
```
- d. Create the OS and RSA directories under `/var/netwitness/<your-zip-file-repo>/11.2.0.0`.

```
mkdir -p /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS
mkdir -p /var/netwitness/<your-zip-file-repo>/11.2.0.0/RSA
```
- e. Unzip the `netwitness-11.2.0.0.zip` file into the `/var/netwitness/<your-zip-file-repo>/11.2.0.0` directory.

```
unzip netwitness-11.2.0.0.zip -d /var/netwitness/<your-zip-file-repo>/11.2.0.0
```

Unzipping `netwitness-11.2.0.0.zip` results in two zip files (`OS-11.2.0.0.zip` and `RSA-11.2.0.0.zip`) and some other files.
- f. Unzip the:
 - i. `OS-11.2.0.0.zip` into the `/var/netwitness/<your-zip-file-repo>/11.2.0.0/OS` directory.

```
unzip /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS-11.2.0.0.zip -d /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS
```

The following example illustrates how the Operating System (OS) file structure appears after

you unzip the file.

	Parent Directory	-
	GeoIP-1.5.0-11.el7.x86_64.rpm	20-Nov-2016 12:49 1.1M
	HostAgent-Linux-64-x86-en_US-1.2.25.1.0163-1.x86_64.rpm	03-Oct-2017 10:07 4.6M
	Lib_Utils-1.00-09.noarch.rpm	03-Oct-2017 10:05 1.5M
	OpenIPMI-libs-2.0.19-15.el7.x86_64.rpm	20-Nov-2016 14:43 502K
	OpenIPMI-modalias-2.0.19-15.el7.x86_64.rpm	20-Nov-2016 14:43 15K
	PyYAML-3.11-1.el7.x86_64.rpm	19-Dec-2017 12:30 160K
	SDL-1.2.15-14.el7.x86_64.rpm	25-Nov-2015 10:39 204K
	acl-2.2.51-12.el7.x86_64.rpm	03-Oct-2017 10:04 81K
	adobe-source-sans-pro-fonts-2.020-1.el7.noarch.rpm	13-Feb-2018 05:10 706K
	alsa-lib-1.1.3-3.el7.x86_64.rpm	10-Aug-2017 10:52 421K
	at-3.1.13-22.el7_4.2.x86_64.rpm	25-Jan-2018 17:56 51K
	atk-2.22.0-3.el7.x86_64.rpm	10-Aug-2017 10:53 258K
	attr-2.4.46-12.el7.x86_64.rpm	03-Oct-2017 10:04 66K

- ii. RSA-11.2.0.0.zip into the /var/netwitness/<your-zip-file-repo>/11.2.0.0/RSA directory.

```
unzip /var/netwitness/<your-zip-file-repo>/11.2.0.0/RSA-11.2.0.0.zip  
-d /var/netwitness/<your-zip-file-repo>/11.2.0.0/RSA
```

The following example illustrates how the RSA version update file structure appears after you unzip the file.

	Parent Directory	-
	MegaCli-8.02.21-1.noarch.rpm	03-Oct-2017 10:07 1.2M
	OpenIPMI-2.0.19-15.el7.x86_64.rpm	03-Oct-2017 10:07 173K
	bind-utils-9.9.4-51.el7_4.2.x86_64.rpm	22-Jan-2018 09:03 203K
	bzip2-1.0.6-13.el7.x86_64.rpm	03-Oct-2017 10:07 52K
	cifs-utils-6.2-10.el7.x86_64.rpm	10-Aug-2017 11:14 85K
	device-mapper-multipath-0.4.9-111.el7_4.2.x86_64.rpm	25-Jan-2018 17:56 134K
	dnsmasq-2.76-2.el7_4.2.x86_64.rpm	02-Oct-2017 19:36 277K
	elasticsearch-5.6.9.rpm	17-Apr-2018 09:37 32M
	erlang-19.3-1.el7.centos.x86_64.rpm	03-Oct-2017 10:07 17K
	fineserver-4.6.0-2.el7.x86_64.rpm	27-Feb-2018 09:11 1.3M
	htop-2.1.0-1.el7.x86_64.rpm	14-Feb-2018 19:23 102K
	i40e-zc-2.3.6.12-1dkms.noarch.rpm	04-May-2018 11:08 399K
	ipmitool-1.8.18-5.el7.x86_64.rpm	10-Aug-2017 12:41 441K
	iptables-services-1.4.21-18.3.el7_4.x86_64.rpm	08-Mar-2018 09:20 51K
	ixgbe-zc-5.0.4.12-dkms.noarch.rpm	04-May-2018 11:08 374K

The external url for the repo is `http://<web server IP address>/<your-zip-file-repo>`.

- g. (Conditional - For Azure) Follow these steps for Azure update.

- i. `mkdir -p /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS/other`
- ii. `unzip nw-azure-11.2-extras.zip -d /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS/other`
- iii. `cd /var/netwitness/<your-zip-file-repo>/11.2.0.0/OS`
- iv. `createrepo .`
- h. Use the `http://<web server IP address>/<your-zip-file-repo>` in response to **Enter the base URL of the external update repositories** prompt from NW 11.2.0.0 Setup program (`nwsetup-tui`) prompt.

Create and Manage Host Groups


The Hosts view provides options for creating and managing groups of hosts. The Groups panel toolbar includes options for creating, editing, and deleting host groups. Once groups are created, you can drag individual hosts from the Hosts panel into a group.

Groups may reflect functional, geographical, project-oriented, or any other organization principle that is useful. A host may belong to more than one group. Here are some examples of possible groupings:

- Group different host types to make it easier to configure and monitor all Brokers, Decoders, or Concentrators.
- Group hosts that are part of the same data flow; for example, a Broker, and all associated Concentrators and Decoders.
- Group hosts according to their geographic region and location within the region. If a major power outage occurs in a location, potentially affected hosts are easily identifiable.


Create a Group

1. Select **ADMIN > Hosts**.
The Hosts view is displayed.
2. In the **Groups** panel toolbar, click **+**.
A field for the new group opens with a blinking cursor.



3. Type the name of the new group in the field (for example, **Geo 1**) and press **Enter**.
The group is created as a folder in the tree. The number next to the group indicates the number of

hosts in that group.



Change the Name of a Group


1. In the Hosts view **Groups** panel, double-click the group name or select the group and click . The name field opens with a blinking cursor.
2. Type the new name of the group and press **Enter**. The name field closes and the new group name is displayed in the tree.

Add a Host to a Group

In the Hosts view **Hosts** panel, select a host and drag the host to a group folder in the Groups panel. The host is added to the group.

View the Hosts in a Group

To view the hosts in a group, click the group in the **Groups** panel. The **Hosts** panel lists the hosts in that group.




Remove a Host from a Group

1. In the Hosts view **Groups** panel, select the group that contains the host that you want to remove. The hosts in that group appear in the Hosts panel.

2. In the **Hosts panel**, select one or more hosts that you want to remove from the group, and in the toolbar, select  > **Remove from Group**.

The selected hosts are removed from the group, but are not removed from the NetWitness Platform user interface. The number of hosts in the group, which is listed near the group name, decreases by the number of hosts removed from the group. The **All** group contains the hosts that were removed from the group.

In the following example, the host group called **Geo 1** does not contain any hosts, because all the hosts in that group are removed.



Delete a Group

1. In the Hosts view **Groups panel**, select the group that you want to delete.
2. Click .

The selected group is removed from the Groups panel. The hosts that were in the group are not removed from the NetWitness Platform user interface. The **All** group contains the hosts from the deleted group.

Search for Hosts

You can search for hosts from a list of hosts in the Hosts view. The Hosts view enables you quickly filter the list of hosts by Name and Host. It is possible to have numerous NetWitness Platform hosts in use for various purposes. Instead of scrolling through the host list, you can quickly filter the host list to locate the hosts that you want to administer.

In the Services view, you can search for a service and quickly find the host that runs that service.

Search for a Host


1. Select **ADMIN > Hosts**.
2. In the **Hosts Panel** toolbar, type a host **Name** or **Hostname** in the **Filter** field.



The Hosts panel lists the hosts that match the names entered in the Filter field.

Find the Host that Runs a Service

1. Select **ADMIN > Services**.
2. In the Services view, select a service. The associated host is listed in the **Host** column for that service.
3. To administer the host in the Hosts view, click the link in the **Host** column for that service. The host associated with the selected service is displayed in the Hosts view.



Execute a Task From the Host Task List

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click  > **View > System**.

Note: The Admin, Config, Orchestration, Security, Investigate, and Respond services do have access to the System view. They only have access to the Explore view. The System view for the service is displayed.

The screenshot shows the RSA Response Center Admin console. The top navigation bar includes tabs for Hosts, Services, Event Sources, Health & Wellness, System, and Security. The 'System' tab is active, and the 'Broker' sub-tab is selected. The console displays the following information:

Broker Service Information

- Name: NW Server (Broker)
- Version: 11.2.0.0 (Rev null)
- Memory Usage: 38376 KB (0.03% of 126 GB)
- CPU: 0%
- Running Since: 2018-May-22 13:51:43
- Uptime: 1 week 1 day 4 hours 14 minutes
- Current Time: 2018-May-30 18:05:43

Appliance Service Information

- Name: NW Server (Host)
- Version: 11.2.0.0 (Rev null)
- Memory Usage: 23076 KB (0.02% of 126 GB)
- CPU: 0%
- Running Since: 2018-May-22 13:51:43
- Uptime: 1 week 1 day 4 hours 13 minutes 59 seconds
- Current Time: 2018-May-30 18:05:42

Broker User Information

- Name: admin
- Groups: Administrators
- Roles: aggregate.manage, concentrator.manage, connections.manage, index.manage, logs.manage, sdk.content, sdk.manage, sdk.meta, sdk.packets, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage

Host User Information

- Name: admin
- Groups: Administrators
- Roles: appliance.manage, connections.manage, logs.manage, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage

Session Information


Session	User	IP Address	Login Time	Active Queries
315	admin	IP Address	2018-May-22 13:51:51	0
342	admin	IP Address	2018-May-22 13:51:52	0
381	escalateduser	IP Address	2018-May-22 13:52:43	0
31612	escalateduser	IP Address	2018-May-30 18:04:38	0

3. In the **Services System** view toolbar, click **Host Tasks**.

The screenshot shows the 'Host Task List' dialog box. It contains the following fields and buttons:


- Task:** A dropdown menu.
- Arguments:** A text input field.
- Run:** A button to execute the task.
- Info:** A text area for additional information.
- Output:** A text area for the task's output.
- Cancel:** A button to close the dialog.

4. In the **Host Task List**, click in the **Task** field to display a drop-down list of tasks that run on a host.



5. Select a task; for example, click **Stop Service**.

The task is displayed in the **Task** field and task description, example arguments, security roles, and parameters are displayed in the **Info** area.




6. Type arguments if necessary and click **Run**.
The command executes and the result is displayed in the **Output** section.

Add and Delete a Filesystem Monitor

When you want a service to monitor traffic on a specific file system, you can select the service and then specify the path. NetWitness Platform adds a filesystem monitor. Once a file system monitor is added to a service, the service continues to monitor traffic on that path until the file system monitor is deleted.

Configure the Filesystem Monitor

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, select **Add Filesystem Monitor**.
In the **Info** area, a brief explanation of the task and the task arguments is displayed.
5. To identify the file system to monitor, type the path in the **Arguments** field. For example:
path=/var/netwitness/decoder/packetdb



The image shows a 'Host Task List' dialog box with the following fields:


- Task:** A dropdown menu with 'Add Filesystem Monitor' selected.
- Arguments:** A text input field containing 'path=/var/netwitness/decoder/packetdb' and a 'Run' button to its right.
- Info:** A text area containing the text: 'parameters: path - <string, {file:The file or directory must exist or be creatable}> Filesystem path to monitor'.
- Output:** An empty text area for displaying results.
- Buttons:** A 'Cancel' button at the bottom right.

6. Click **Run**.
The result is displayed in the **Output** area. The service begins to monitor the file system and continues to monitor it until you delete the filesystem monitor.

Delete a Filesystem Monitor

1. Navigate to the **Host Task List** dialog.
2. In the **Host Task List**, select **Delete Filesystem Monitor**.
In the **Info** area, a brief explanation of the task and the task arguments is displayed.

3. To identify the filesystem to stop monitoring, type the path in the **Arguments** field. For example:
path=/var/netwitness/decoder/packetdb

A screenshot of the 'Host Task List' dialog box. It has a title bar with a close button. Inside, there are four sections: 'Task' with a dropdown menu showing 'Delete Filesystem Monitor'; 'Arguments' with a text input field containing 'path=/var/netwitness/decoder/packetdb' and a 'Run' button to its right; 'Info' with a text area showing 'Delete a filesystem monitor' and 'Example arguments: path=/var/netwitness/decoder/packetdb'; and 'Output' with an empty text area. A 'Cancel' button is at the bottom right.

4. Click **Run**.
The result is displayed in the **Output** area. The service stops monitoring the file system.

Reboot a Host

Under certain conditions, you must reboot a host; for example, after installing a software upgrade. This procedure uses a Host Task List message to shut down and restart a host.

NetWitness Platform also offers other options for shutting down a host:


- To shut down and restart a host through an attached service, go to the Hosts view from a service in the Services view (see [Search for Hosts](#)) and then follow the *Shut Down and Restart a Host from the Hosts View* procedure below.
- To shut down the physical host without restarting, see [Shut Down Host](#).

Shut Down and Restart a Host from the Hosts View

1. Select **ADMIN > Hosts**.
2. In the **Hosts** panel, select a host.
3. Select  **Reboot Host** from the toolbar.

Shut Down and Restart a Host from the Host Task List

1. Select **ADMIN > Services**.
2. In the **Services** panel, select a service and click   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, select **Reboot Host** in the **Task** field.
No arguments are required.



5. Click **Run**.
The host is rebooted and the result is displayed in the **Output** area.

Set Host Built-In Clock


After a shutdown or battery failure, it may be necessary to set the local clock on a host. The Set Host Built-In Clock task resets the clock time.

Set the Time on the Local Clock

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.

4. In the **Host Task List**, select **Set Host Built-In Clock**. Help for the task is displayed in the **Info** area.
5. Enter the date and time arguments in the **Arguments** field; for example, to specify October 31, 2017 at 11:59:59 PM, type:

set=20171031T235959



The screenshot shows a window titled "Host Task List". It has a "Task" dropdown menu with "Set Host Built-In Clock" selected. Below it is an "Arguments" text input field containing "set=20171031T235959" and a "Run" button. The "Info" section contains the text "Set the appliance local clock" and "Example arguments: set=20091231T235959". At the bottom is an empty "Output" text area and a "Cancel" button.

6. Click **Run**.
The clock is set to the specified time and a message is displayed in the **Output** area.

Set Network Configuration

When a configured core host needs its address changed, you can set a new network address, subnet mask, and gateway for the host using the **Set Network Configuration** message in the **Host Task List**.

Caution: The change goes into effect immediately, and the host is disconnected from NetWitness Platform. You must then add the host to NetWitness Platform again using the new network address.

Specify the Network Address for a Host

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click   > **View System**.
The System view for the service is displayed.
3. In the **Services System view** toolbar, click **Host Tasks**.
4. In the **Host Task List**, click **Set Network Configuration**.
The task is displayed in the **Task** field and help is displayed in the **Info** area.

- Enter the arguments in the **Arguments** field. For example:
`mode=static address=192.168.0.20 netmask=255.255.255.0 gateway=192.168.0.1`

The image shows a 'Host Task List' dialog box. It has a title bar with a close button. Inside, there are four sections: 'Task' with a dropdown menu set to 'Set Network Configuration'; 'Arguments' with a text input field containing 'mode=static address=192.168.0.20 netmask=25' and a 'Run' button; 'Info' with a text area containing 'Set network parameters. This will disconnect you from the appliance.' and 'Example arguments:'; and 'Output' with an empty text area. A 'Cancel' button is at the bottom right.

- Click **Run**.
 The task executes and the result is displayed in the **Output** area. The host is disconnected from NetWitness Platform. You must add the host again with the new address.

Note: If the mode is DHCP, there may be no way to determine the new address. You may have to connect to the host directly to determine the new address.

Set Network Time Source

When setting the clock source for a host, set the hostname or address of an NTP server to be the network clock source for the host. If the host is using a local clock source, you must specify **local** here to allow **Set the Local Clock Source** to be effective.

Specify the Network Clock Source

- Select **ADMIN > Services**.
- In the **Services** grid, select a service and click   **View > System**.
 The System view for the service is displayed.
- In the **Services System** view toolbar, click **Host Tasks**.

4. In the **Host Task List**, select **Set Network Time Source**.

Host Task List

Task: **Set Network Time Source** ▼

Arguments: **Run**

Info: Set the clock source for this appliance
Example arguments:
source=tictoc.localdomain

Output:

Cancel

5. Do one of the following:
 - Type the hostname or address of the NTP server to serve as the clock source for this host; for example: **source=tictoc.localdomain**
 - If you want to use the host clock as a clock source, type:
source=local
6. Click **Run**.
The clock source is set and a message is displayed in the **Output** area.

Note: If you specified a NTP clock source of **local**, the host clock serves as the clock source and the time is configured using [Set Host Built-In Clock](#).


Set SNMP

Set SNMP in the Host Task List enables or disables the SNMP service on a host. For a host to receive SNMP notifications, enable the SNMP service. If you are not using SNMP for NetWitness Platform notifications, it is not necessary to enable the service.

Toggle SNMP Service on the Host


1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click > **View > System**.
The System view for the service is displayed.
3. In the **Services System view** toolbar, click **Host Tasks**.

4. In the **Host Task List**, select **setSNMP**.
In the **Info** area, a brief explanation of the task and the task arguments is displayed.
5. Do one of the following:
 - If you want to disable the service, type **enable=0** in the **Arguments** field.



The screenshot shows the 'Host Task List' dialog box. The 'Task' dropdown is set to 'setSNMP'. The 'Arguments' text box contains 'enable=0'. The 'Info' section displays 'Enabled or Disable the SNMP service' and 'Example arguments: enable=1'. The 'Output' section is empty. A 'Run' button is next to the 'Arguments' field, and a 'Cancel' button is at the bottom right.

- If you want to enable the service, type **enable=1** in the **Arguments** field.



The screenshot shows the 'Host Task List' dialog box. The 'Task' dropdown is set to 'setSNMP'. The 'Arguments' text box contains 'enable=1'. The 'Info' section displays 'Enabled or Disable the SNMP service' and 'Example arguments: enable=1'. The 'Output' section is empty. A 'Run' button is next to the 'Arguments' field, and a 'Cancel' button is at the bottom right.


6. Click **Run**.
The result is displayed in the **Output** area.

Set Syslog Forwarding

You can configure Syslog forwarding to forward the operating system logs of your NetWitness Platform Hosts to a remote syslog server. You can use the Set Syslog Forwarding task in the Host Task List to enable or disable syslog forwarding.

Set Up and Start Syslog Forwarding

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, select **Set Syslog Forwarding**.
In the **Info** area, a brief explanation of the task and the task arguments is displayed.



Host Task List

Task: Set Syslog Forwarding

Arguments: Run

Info: Enable or disable syslog forwarding
 Example arguments:
 host=loghost.localdomain

Output:

Cancel

5. In the **Arguments** field, do any one of the following.
 - To enable syslog forwarding, specify any one of the following formats:
 - **host=<loghost>.<localdomain>** (for example, host=syslogserver.local).
 - **host=<loghost>.<localdomain>:<port>** (for example, host=syslogserver.local:514).
 - **host=<IP>** (for example, host=10.31.244.244).
 - **host=<IP>:<port>** (for example, host=10.31.244.244:514).

The following table lists the parameters used to enable syslog forwarding.

Parameter	Description
loghost	The host name of the remote syslog server.
localdomain	The domain of the remote syslog server.
port	IP address of the remote syslog server.
IP	The port number on which the remote syslog server receives a syslog messages.

- To disable syslog forwarding, type **host=disable**.
6. Click **Run**.
The result is displayed in the **Output** area.

Once syslog forwarding is enabled or disabled, the `/etc/rsyslog.conf` file is updated automatically to enable or disable syslog forwarding to the remote syslog destination and the syslog service is restarted.

If you enable syslog forwarding, the logs from the configured service are forwarded to the defined syslog server and continues forwarding until disabled.

Note: You can now log in to the remote syslog server and verify if the messages are being received from the NetWitness Platform services configured for syslog forwarding.


Show Network Port Status

The Show Network Port Status task in the Host Task List gives you the status of all configured ports on the host.

Display the Network Port Status

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and   **> View > System**.
The System view for the selected service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, click **Show Network Port Status**.
The task is displayed in the **Task** field, and information about the task is displayed in the **Info** area.
5. To execute the task, click **Run**.

The status for each port on the host is displayed in the **Output** area.



Host Task List

Task: Show Network Port Status

Arguments: Run

Info: Show interface information
No arguments required

Output: lo: link up
eth0: link up


Cancel

Show Serial Number

The Show Serial Number task in the Host Task List displays the serial number of a host.

Show the Serial Number

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, select **Show Serial Number**.
In the **Info** area, a brief explanation of the task and the task arguments is displayed.
5. No arguments are required for this task. Click **Run**.
The serial number of the selected host is displayed in the **Output** area.



The screenshot shows a dialog box titled "Host Task List" with a close button (X) in the top right corner. Inside the dialog, there are four main sections: "Task", "Arguments", "Info", and "Output". The "Task" section has a dropdown menu currently showing "Show Serial Number". The "Arguments" section has an empty text input field and a "Run" button to its right. The "Info" section contains a text area with the text "Retrieve the appliance serial number" and "No arguments required", with a vertical scrollbar on the right. The "Output" section has a text area displaying "serial-number". At the bottom right of the dialog is a "Cancel" button.

Shut Down Host


Under certain circumstances; for example, a hardware upgrade or an extended power outage that exceeds backup power capacity, it may be necessary to shut down a physical host. When you shut down a host, all services running on the host are stopped and the physical host turns off.

The physical host does not restart automatically. Use the power switch to restart the host. Once the physical host restarts, the host and services are configured to restart automatically.

[Reboot a Host](#) to start and stop a host without shutting down the host.

Shut Down the Host

1. In the Host Task List dialog, select **Shut Down Host** in the **Task** field.



The image shows a 'Host Task List' dialog box. It has a title bar with a close button. Inside, there are four sections: 'Task', 'Arguments', 'Info', and 'Output'. The 'Task' section has a dropdown menu with 'Shut Down Host' selected. The 'Arguments' section has an empty text box and a 'Run' button. The 'Info' section has a text area containing 'Shut down this appliance' and 'No arguments required'. The 'Output' section has an empty text box. At the bottom right, there is a 'Cancel' button.

2. To execute the task, click **Run**.
The host shuts down, and the host turns off.

Stop and Start a Service on a Host


The Host Task List has two options for stopping and starting a service on a host. When you stop a service using the **Stop Service** message, all processes of the service are stopped and users connecting to the service are disconnected. Unless there is a problem with the service, it restarts automatically. This is the same as the **Shutdown Service** option in the Services System view.

If a service does not restart automatically after being stopped, you can restart it manually using the **Start Service** message.

Stop a Service on a Host

1. Select **ADMIN > Services**.
2. In the **Services** grid, select a service and click   > **View > System**.
The System view for the service is displayed.
3. In the **Services System** view toolbar, click **Host Tasks**.
4. In the **Host Task List**, click **Stop Service**.
The task is displayed in the **Task** field, and information about the task is displayed in the **info** area.

5. Specify the service (decoder, concentrator, broker, logdecoder, logcollector) to stop in the **Arguments** field; for example, **service=decoder**.




The **Host Task List** dialog box is shown. The **Task** dropdown menu is set to **Stop Service**. The **Arguments** text field contains **service=decoder**. The **Info** section displays: "Stop a Netwitness service on this appliance" and "Example arguments: service=decoder". The **Output** area is empty. A **Run** button is to the right of the **Arguments** field, and a **Cancel** button is at the bottom right.

6. To execute the task, click **Run**.
The service stops and the status is displayed in the **Output** area. All processes of the service are stopped and users connecting to the service are disconnected. Unless there is a problem with the service, it restarts automatically.

Start a Service on a Host

1. In the **Host Task List**, select **Start Service** from the Task drop-down menu.
The task is displayed in the **Task** field, and information about the task is displayed in the **info** area.
2. Specify the service (decoder, concentrator, broker, logdecoder, logcollector) to start in the **Arguments** field; for example, **service=decoder**



The **Host Task List** dialog box is shown. The **Task** dropdown menu is set to **Start Service**. The **Arguments** text field contains **service=decoder**. The **Info** section displays: "Start a Netwitness service on this appliance" and "Example arguments: service=decoder". The **Output** area is empty. A **Run** button is to the right of the **Arguments** field, and a **Cancel** button is at the bottom right.

3. To execute the task, click **Run**.

The service starts and the status is displayed on the **Output** area.

Add, Replicate, or Delete a Service User

You must add a user to a service for:

- Aggregation
- Accessing the service with the:
 - Thick client
 - REST API

Note: This topic does not apply to users who access services through the user interface on NetWitness Server. You must add those users to the system, not a service. For details, see the **Set Up a User** topic in *System Security and User Management*.

For each service user, you can:

- Configure user authentication and query handling properties for the service
- Make the user a member of a role, which has a set of permissions the user receives
- Replicate the user account to other services
- Change the service user password on selected services

[Change a Service User Password](#) provides instructions for changing the service user password across services.

Procedures


Access the Security View

Each of the following procedures starts in the Services Security view.

To navigate to the Services Security view:

1. In NetWitness Platform, go to **ADMIN > Services**.

2. Select a service, then click  > **View > Security**.
The Security view for the selected service is displayed with the Users tab open.



The screenshot shows the RSA NetWitness Platform interface. The top navigation bar includes tabs for Hosts, Services, Event Sources, Health & Wellness, System, and Security. The 'Security' tab is active, and the 'Users' sub-tab is selected. On the left, a list of users is shown with 'admin' selected. The main area displays the 'User Information' form for the 'admin' user. The form includes fields for Name (Administrator), Username (admin), Password, Confirm Password, Email, and Description (Administrator account for this service). Below this is the 'User Settings' section with fields for Auth Type (NetWitness Platform), Core Query Timeout (60), Query Prefix, and Session Threshold (0). At the bottom is the 'Role Membership' section with a list of roles: Groups, Administrators (checked), Aggregation, Analysts, Data_Privacy_Officers, Malware_Analysts, Operators, and SOC_Managers.

Note: For NetWitness Platform 10.4 and earlier service versions, in the User Settings section, the **Query Level** field is displayed instead of **Core Query timeout**.

Add a Service User

1. On the **Users** tab, click .
2. Type the user name to access the service, then press **Enter**.
The User Information section displays the user name and the rest of the fields are available for editing.
3. Type the password for logging on to the service in the **Password** and **Confirm Password** fields.
4. (Optional) Provide additional information:

- **Name** for logging on to NetWitness Platform
 - **Email** address
 - **Description** of the user
5. In the User Settings section, select the following information:
- **Authentication Type**
 - If NetWitness Platform authenticates the user, select NetWitness.
 - If Active Directory or PAM is configured on NetWitness Server to authenticate the user, select External.
 - **Core Query Timeout** is the maximum number of minutes a user can run a query on the service. This field applies to NetWitness Platform 10.5 and later service versions and does not appear for 10.4 and earlier versions.
6. (Optional) Specify additional query criteria:
- **Query Prefix** filters queries. Type a prefix to restrict results the user sees.
 - **Session Threshold** controls how the service scans meta values to determine session counts. Any meta value with a session count that is above the threshold stops its determination of the true session count.
7. In the **Role Membership** section, select each role to assign to the user. When a user is a member of a role on a service, the user has the permissions assigned to the role.
8. To activate the new service user, click **Apply**.

Replicate a User to Other Services

1. In the Users tab, select a user and click   > **Replicate**.
The Replicate Users to Other Services dialog is displayed.

Replicate User to other services

Please enter and confirm the service user password. The entire service user account replicates to the selected services. The user password also changes on each selected service.

Password

Confirm Password

☐	Name ^	Address	Type
☐	- Broker		Broker
☐	- Conc...		Concentrator
☐	- Archi...		Archiver
☐	- Work...		Workbench
☐	- Log C...		Log Collector
☐	- Log ...		Log Decoder
☐	- Wareh...		Warehouse C...
	NW - Malware A		Malware A

Cancel Replicate

2. Enter and confirm the password.
3. Select each service to which you are replicating the user.
4. Click **Replicate**.

Delete a Service User

1. On the **Users** tab, select the **Username** and click . NetWitness Platform requests confirmation that you want to delete the selected user.
2. To confirm, click **Yes**.

Add a Service User Role

There are pre-configured roles in NetWitness Platform that are installed on the server and on each service. You can also add custom roles. The following table lists the pre-configured system roles and their permissions.

Role	Permission
Administrators	Full system access
Operators	Access to configurations but not to meta and session content
Analysts	Access to meta and session content but not to configurations

Role	Permission
SOC_Managers	Same access as Analysts and additional permissions to handle incidents
Malware_Analysts	Access to malware events and to meta and session content
Data_Privacy_Officers	Access to meta and session content and configuration options that manage obfuscation and viewing of sensitive data within the system (see Data Privacy Management).

You must add a service role when you have added a:

- **Service** user or users that requires a new set of permissions.
- **Custom role on NetWitness Server** because trusted connections require that the same custom role exists both on the server and on each service the custom role will access. The names must be identical. For example, if you add a Junior Analysts role on the server then you must add a Junior Analysts role on each service the role will access. For more information, see the **Add a Role and Assign Permissions** topic in *System Security and User Management*.

There is also a pre-configured **Aggregation** service role. Aggregation Role and Service User Roles and Permissions provide additional information.

Procedure


To add a service user role and assign permissions to it:

1. In NetWitness Platform, go to **ADMIN > Services**.
2. Select a service, then  > **View > Security**.

The Security view for the selected service is displayed with the Users tab open.

3. Select the **Roles** tab and click **+**.

The Services Security view is displayed and five pre-configured roles are already listed.



4. Click **+**, type the **Role Name** and press **Enter**.
The Role Name is displayed above a list of **Role Permissions**.
5. Select each permission the role will have on the service.
6. Click **Apply**.

You can add service users to it in the **Users** tab.

Change a Service User Password


This procedure allows administrators to change the password of a service user and replicate the new password to all Core services with that user account defined. It replicates only the password change to the Core services selected and does not replicate the entire user account. Administrators can also change the password of the **admin** account on the Core services.

Note: The Change Password option does not apply to external users.

To change the password of a service user:

1. In NetWitness Platform, go to **ADMIN > Services**.
The Administration Services view is displayed.
2. Select a service, then click  > **View > Security**.
The Security view for the selected services is displayed.

- In the **Users** tab, select a user and select **Change Password** from the actions icon. The **Change Password** dialog is displayed.



Change Password

Please enter and confirm the service user password. Only the user password changes on the selected services. No other user attributes will replicate to the services

Password

Confirm Password

☐	Name ^	Address	Type
☐	S5EndpointLohHyb - Log Decoder		Log Decoder
☐	S5LogDecoder - Log Collector		Log Collector
☐	S5LogDecoder - Log Decoder		Log Decoder
☐	S5LogHybrid - Concentrator		Concentrator
☐	S5LogHybrid - Log Collector		Log Collector
☐	S5LogHybrid - Log Decoder		Log Decoder
☐	S5MalwareAnalysis - Broker		Broker
☐	S5NWDecoder - Decoder		Decoder
☐	S5PacketHybrid - Concentrator		Concentrator
☐	S5PacketHybrid - Decoder		Decoder
☒	VLC2514 - Log Collector		Log Collector

Cancel Change Password

- Type a new password for the user and confirm the password.
- Select the services where you want the user password to change.
- Click **Change Password**.
The status of the password change on the selected services is displayed.

Create and Manage Service Groups

The Administration Services view provides options to create and manage groups of services. The Services panel toolbar includes options to create, edit, and delete service groups. Once groups are created, you can drag individual services from the Services panel into a group.


Groups may reflect functional, geographical, project-oriented, or any other organization principle that is useful. A service may belong to more than one group. Here are some examples of possible groupings.

- Group different service types to make it easier to configure and monitor all Brokers, Decoders, or Concentrators.


- Group services that are part of the same data flow; for example, a Broker, and all associated Concentrators and Decoders.
- Group services according to their geographic region and location within the region. If a major power outage occurs in a location, potentially affected services are easily identifiable.

Create a Group

1. In NetWitness Platform, go to **ADMIN > Services**.
The Administration Services view is displayed.
2. In the **Groups** panel toolbar, click **+**.
A field for the new group opens with a blinking cursor.



3. Type the name of the new group in the field (for example, **A New Group**) and press **Enter**.
The group is created as a folder in the tree. The number next to the group indicates the number of services in that group.



Change the Name of a Group

1. In the **Services** view **Groups** panel, double-click the group name or select the group and click . The name field opens with a blinking cursor.
2. Type the new name of the group and press **Enter**. The name field closes and the new group name is displayed in the tree.

Add a Service to a Group

In the **Services** view **Services** panel, select a service and drag the service to a group folder in the groups panel; for example, **Log Collectors**.

The service is added to the group.

View the Services in a Group

To view the services in a group, click the group in the **Groups** panel.


The **Services** panel lists the services in that group.

Remove a Service from a Group

1. In the **Services** view **Groups** panel, select the group that contains the service that you want to remove. The services in that group appear in the **Services** panel.
2. In the **Services** panel, select one or more services that you want to remove from the group, and in the toolbar, select  > **Remove from Group**.

The selected services are removed from the group, but are not removed from the NetWitness Platform user interface. The number of services in the group, which is listed near the group name, decreases by the number of services removed from the group. The **All** group contains the services that are removed from the group.

In the following example, the service group called **A New Group** does not contain any services, because the service in that group is removed.



Delete a Group

1. In the Services view **Groups** panel, select the group that you want to delete.
2. Click .
The selected group is removed from the Groups panel. The services that were in the group are not removed from the NetWitness Platform user interface. The **All** group contains the services from the deleted group.

Duplicate or Replicate a Service Role

An efficient way to add a new service role is to duplicate a similar role, save it with a new name and revise the permissions that are already assigned. For example, you could duplicate the Analysts role. Then, save it as **JuniorAnalysts** and modify the permissions.

The quick way to add an existing role to other services is to replicate the role. For example, you could replicate the **JuniorAnalysts** role that exists on a broker to a concentrator and log decoder.


Each of the following procedures starts in the Services Security view.

To navigate to the Services Security view:

1. In NetWitness Platform, go to **ADMIN > Services**.
2. Select a service, then click  > **View > Security**.
The Security view for the selected service is displayed with the Users tab open.
3. Select the **Roles** tab.

Duplicate a Service Role

1. In the Roles tab, select the role you want to duplicate.



2. Click  **Duplicate Role**.
3. Type a new name and click **Apply**.
4. Select the new role.
5. In the **Role Permissions** section, select or deselect permissions to modify what the new role can do.

Replicate a Role

1. In the **Roles** tab, select the role you want to replicate and click **Replicate**.
2. In the **Replicate Role to Other Services** dialog, select each service on which to add the role.
3. Click **Replicate**.

Edit Core Service Configuration Files

The service configuration files for Decoder, Log Decoder, Broker, Concentrator, Archiver, and Workbench services are editable as text files. In the Service Config view > Files tab, you can:

- View and edit a service configuration file that the NetWitness Platform system is currently using.
- Retrieve and restore the latest backup of the file you are editing.

- Push the open file to other services.
- Save changes made to a file.

The files available to edit vary depending upon the type of service being configured. The files that are common to all core services are the:

- service index file
- netwitness file
- crash reporter file
- scheduler file

In addition, the Decoder has files that configure parsers, feed definitions, and a wireless LAN adapter.


Note: The default values in these configuration files are good for the most common situations, however some editing is necessary for optional services, such as the crash reporter or scheduler. Only administrators with a good understanding of the networks and the factors that affect the way services collect and parse data should make changes to these files in the Files tab.

Edit a Service Configuration File

To edit a file:

1. In NetWitness Platform, go to **ADMIN > Services**.
2. In the Services grid, select a service.
3. Select  > **View > Config**.
The Service Config view is displayed with the General tab open.
4. Click the **Files** tab.
The selected service, such as Concentrator, appears in the drop-down list on the right.
5. (Optional) To edit a file for the host instead of the service, select **Host** in the drop-down list.

- Choose a file from the **Please Select A File To Edit** drop-down list.
The file content is displayed in edit mode.



- Edit the file and click **Apply**.

The current file is overwritten and a backup file is created. The changes go into effect after the service is restarted.

Revert to a Backup Version of a Service Configuration File

After you make changes to a configuration file, save the file, and restart the service, a backup file is available. To revert to a backup of a configuration file:

- Select a configuration file by completing steps 1-6 of the procedure at the beginning of this topic.
- Click  **Get Backup**.
The backup file opens in the text editor.

- To revert to the backup version, click **Save**.

The changes go into effect after the service is restarted.

Push a Configuration File to Other Services

Once you have edited a service configuration file, you can push the same configuration to other services of the same type.

- Select a configuration file by completing steps 1-6 of the [Edit Service Configuration Files](#) procedure at the beginning of this topic.
- Click  **Push**. The Select Services dialog is displayed.

3. Select each service to push the configuration file on it.

Each service must be the same type as the one you selected in the Services view.

Caution: If you decide not to push the configuration file, click **Cancel**.

4. To push the configuration file to all selected services, click **OK**.

The configuration file is pushed to all selected services.

Configure the Task Scheduler

Scheduler file

You can edit the **scheduler** file that in the Service Config view > Files tab. This file configures the built-in task scheduler for a service. The task scheduler can automatically send messages at predefined intervals or specific times of the day.

Scheduler task syntax

A task line in the scheduler file consists of the following syntax, where **<Value>** has no spaces:

```
<ParamName>=<Value>
```

if **<Value>** has any spaces, this is the syntax:

```
<ParamName>="<Value>"
```

In each task line, these guidelines apply:

- Parameter **time** or one of the interval parameters (**seconds**, **minutes** or **hours**) is required.
- Escape special characters with a \ (backslash).

Task line parameters

The following task line parameters are accepted by the scheduler.

Syntax	Description
daysOfWeek: <string, optional, {enum-any:sun mon tue wed thu fri sat all}>	The days of week to execute a task. The default value is all.
deleteOnFinish: <bool, optional>	Delete the task when it has successfully finished.
hours: <uint32, optional, {range:1 to 8760}>	The number of hours between executions.
logOutput: <string, optional>	Output the response to log using the specified module name.
minutes: <uint32, optional, {range:1 to 525948}>	The number of minutes between executions.
msg: <string>	The message to send the node.
params: <string, optional>	The parameters for the message.
pathname: <string>	The path of the node that receives the message.
seconds: <uint32, optional, {range:1 to 31556926}>	The number of seconds between executions.

Syntax	Description
time: <string>	The time of execution in HH::MM:SS format (local time of this server).
timesToRun: <uint32, optional>	How many times to run because service start, 0 = means unlimited (default).

Messages

The following are the message strings to use in the Task Scheduler **msg** parameter.

Message	Description
addInter	Add a task to run at a defined interval. For example, this message runs the /index save command every 6 hours: addInter hours=6 pathname=/index msg=save
addMil	Add a task to run at a specific time of day or even day(s) of the week. For example, this message runs the /index save command at 1 AM every business day: addMil time= 01:00:00 pathname=/index msg=save daysOfWeek=mon,tue,wed,thu,fri
delSched	Deletes an existing scheduled task. The id parameter of the task must be retrieved from the print message.
print	Prints all scheduled tasks.
replace	Assign all scheduled tasks in one message, deleting any existing tasks.
save	Save node

Sample Task Line

The following example task line in the scheduler file downloads the feeds package file (**feeds.zip**) to the selected Decoder every 120 minutes from the feeds host server:

```
minutes=120 pathname=/parsers msg=feed params="type\=wget
file\=http://feedshost/nwlive/feeds.zip"
```

Edit a Service Index File

This topic provides important information and guidelines for configuring service custom index files, which are editable in the Service Config view > Files tab.

The index file, along with other configuration files, controls operation of each core service. Accessing the index file through the Service Config view in NetWitness Platform opens the file in a text editor, where you can edit the file.

Note: Only administrators with a thorough and comprehensive understanding of core service configuration are qualified to make changes to an index file, which is one of the central configuration files for the appliance service. Changes made should be consistent across all core services. Invalid entries or a misconfigured file can prevent the system from starting and can require the assistance of RSA Support to bring the system back into a working state.

These are the index files:

- `index-broker.xml`, and `index-brokereustom.xml`
- `index-concentrator.xml`, and `index-concentrator eustom.xml`
- `index-decoder.xml`, and `index-decodereustom.xml`
- `index-logdecoder.xml`, and `index-logdecodereustom.xml`
- `index-archiver.xml`, and `index-archiver eustom.xml`
- `index-workbench.xml`, and `index-workbench eustom.xml`

Index and Custom Index Files

All customer-specific index changes are made in `index-<service>-custom.xml`. This file overrides any settings in `index-<service>.xml`, which is solely controlled by RSA.

The custom index file, `index-<service>-custom.xml`, allows creation of custom definitions or overrides of your own language keys that are not overwritten during the upgrade process.

- Keys that are defined in `index-<service>-eustom.xml` replace the definitions found in `index-<service>.xml`.
- Keys that are added to `index-<service>-eustom.xml` and not found in `index-<service>.xml` are added to the language as a new key.

Some common applications for editing the index file are:

- To add new custom meta keys to add new fields to the NetWitness Platform user interface.
- To configure protected meta keys as part of a data privacy solution as described in the *Data Privacy Management* guide.
- To adjust the NetWitness Platform core database query performance as described in the *NetWitness Platform Core Database Tuning Guide*.

Caution: Never set the index level to `IndexKeys` or `IndexValues` on a Decoder if you have a Concentrator or Archiver aggregating from the Decoder. The index partition size is too small to support any indexing beyond the default `time` meta key.

Enable Crash Reporter Service

The Crash Reporter is an optional service for NetWitness Platform services. When activated for any of the core services, the Crash Reporter automatically generates a package of information to be used for diagnosing and solving the problem that resulted in the service failure. The package is automatically sent to RSA for analysis. The results are forwarded to RSA support for any further action.

The information package sent to RSA does not contain captured data. This information package consists of the following information:

- Stack trace
- Logs
- Configuration settings
- Software version
- CPU information

- Installed RPMs
- Disk geometry

The Crash Reporter crash analysis can be activated for any core product.

The **crashreporter.cfg** File

One of the files available for editing in the Service Config view > Files tab is **crashreporter.cfg**, the Crash Reporter Client Server configuration file.

This file is used by the script that checks, updates, and builds crash reports on the host. The list of products to monitor can include Decoders, Concentrators, hosts, and Brokers.

This table lists the settings for the **crashreporter.cfg** file.

Setting	Description
applicationlist=decoder, concentrator, host	Define the list of products to monitor.
sitedir=/var/crashreporter	Location of the site directory for the report.
webdir=/usr/share/crashreporter/Web	Location of the web directory.
devdir=/var/crashreporter/Dev	Location of the development directory.
datadir=/var/crashreporter/data	Location of the directory storing data files.
perldir=/usr/share/crashreporter/perl	Location of the perl files.
bindir=/usr/share/crashreporter/bin	Location of the binary executables.
libdir=/usr/share/crashreporter/lib	Location of the binary libraries.
cfgdir=/etc/crashreporter	Location of the configuration files.
logdir=/var/log/crashreporter	Location of the log files.
scriptdir=/usr/share/crashreporter/scripts	Location of the directory containing scripts.
workdir=/var/crashreporter/work	Location of the process work directory.
sqldir=/var/crashreporter/sql	Location where created sql files are placed.
reportdir=/var/crashreporter/reports	Location where temporary reports are created.
packagedir=/var/crashreporter/packages	Location of the created package files.
gdbconfig=/etc/crashreporter/crashreporter.gdb	Location of the gdb configuration file.

Setting	Description
corewaittime=30	Define the number of seconds to wait after finding a core to determine if the core is still being written.
cyclewaittime=10	Define the number of minutes to wait between search cycles
deletecores=1	Specify if the core files should be deleted after report. 0 = No 1 = Yes NOTE: Until the core file is deleted, it is reported each time crashreporter is restarted.
deletereportdir=1	Specify if the report directory should be deleted after the report. Useful to view core reports on box. 0 = No 1 = Yes NOTE: If not deleted, the directory will be included in each subsequent package.
debug=1	Specify whether debugging messages are turned on or off in the crashreporter logging output. 0 = No 1 = Yes
posturl=https://www.netwitnesslive.com/crash...ter/submit.php	Define the webserver post url.
postpackages=0	Specify if the packages should be posted to the webserver. 0 = No 1 = Yes
deletepackages=1	Specify if packages should be deleted after they are posted to webserver. 0 = No 1 = Yes

Configure the Crash Reporter Service

To configure the Crash Reporter service:


1. Select **ADMIN > Services**.
2. Select a service and click   > **View > Config**.
3. Select the **Files** tab.
4. Edit **crashreporter.cfg**.

5. Click **Save**.
6. To display the Service System view, select **Config > System**.
7. To restart the service, click  **Shutdown Service**.
The service shuts down and restarts.

Start and Stop the Crash Reporter Service

To start the Crash Reporter Service:

1. Select **ADMIN > Services**.
2. Select a service and click   > **View > System**.
3. In the toolbar, click  **Host Tasks**.
The Host Task List is displayed.
4. In the Task drop-down list, select **Start Service**.
5. In the Arguments field, type **crashreporter**, then click **Run**.



The Host Task List dialog box is shown. It has a title bar 'Host Task List' with a close button. Inside, there are four sections: 'Task' with a dropdown menu showing 'Start Service'; 'Arguments' with a text input field containing 'crashreporter' and a 'Run' button; 'Info' with a text area containing 'Start a Netwitness service on this appliance' and 'Example arguments: service=decoder'; and 'Output' with an empty text area. A 'Cancel' button is at the bottom right.

The Crash Reporter service is activated and remains active until you stop it.

To stop the Crash Reporter service, select **Stop Service** from the Task drop-down list.

Maintain the Table Map Files

The table mapping file provided by RSA, `table-map.xml`, is a very significant part of the Log Decoder. It is a meta definition file which also maps the keys used in a log parser to the keys in the metadb.

Note: Do not edit the `table-map.xml` file. If you want to make changes to the table-map, make them in the `table-map-custom.xml` file. The latest `table-map.xml` file is available on Live and RSA updates it as required. If you make changes to the `table-map.xml` file, they can be overwritten during an upgrade of service or content.

In the `table-map.xml`, some meta keys are set to `Transient` and some are set to `None`. To store and index a specific meta key, the key must be set to `None`. To make changes to the mapping, you need to create a copy of the file named `table-map-custom.xml` on the Log Decoder and set the meta keys to `None`.

For meta key indexing:

- When a key is marked as `None` in the `table-map.xml` file in the Log Decoder, it is indexed.
- When a key is marked as `Transient` in the **`table-map.xml`** file in the Log Decoder, it is not indexed. To index the key, copy the entry to the `table-map-custom.xml` file and change the keyword `flags="Transient"` to `flags="None"`.
- If a key does not exist in the `table-map.xml` file, add an entry to the `table-map-custom.xml` file in the Log Decoder.

Caution: Do not update the `table-map.xml` file because an upgrade can overwrite it. Add all of the changes that you want to make to the **`table-map-custom.xml`** file.

Prerequisites


If you do not have a `table-map-custom.xml` file on the Log Decoder, create a copy of `table-map.xml` and rename it to `table-map-custom.xml`.

Procedure

To verify and update the table mapping file:

1. Go to **ADMIN > Services**.
2. In the Services grid, select a Log Decoder and click   > **View > Config**.

- Click the **Files** tab and select the `table-map.xml` file.



- Verify that the flags keywords are set correctly to either `Transient` or `None`.
- If you need to change an entry, do not change the `table-map.xml` file. Instead, copy the entry, select the `table-map-custom.xml` file, find the entry in the `table-map-custom.xml` file and change the flags keyword from `Transient` to `None`.
For example, the following entry for the `hardware.id` meta key in the `table-map.xml` file is not indexed and the flags keyword shows as `Transient`:

```
<mapping envisionName="hardware_id" nwName="hardware.id"
flags="Transient"/>
```

 To index the `hardware.id` meta key, change the flags keyword from `Transient` to `None` in the `table-map-custom.xml`:

```
<mapping envisionName="hardware_id" nwName="hardware.id" flags="None"/>
```
- If an entry does not exist in the `table-map.xml` file, add an entry to the `table-map-custom.xml` file.
- After making your changes to the `table-map-custom.xml` file, click **Apply**.


Caution: Before changing the table mapping files, carefully consider the effect of changing the index from `Transient` to `None` because it can impact the available storage and performance of the Log Decoder. For this reason, only certain meta keys are indexed out-of-the-box. Use the `table-map-custom.xml` file for different use cases.

Edit or Delete a Service

You can edit service settings, such as changing the host name or port number, or delete a service that you no longer need.

Each of the following procedures starts in the Services view.

To navigate to the Services view, in NetWitness Platform, go to **ADMIN > Services**.



Procedures

Edit a Service

1. In the Services view, select a service and click or > **Edit**.
The **Edit Service** dialog is displayed. It shows only the fields that apply to the selected service.

2. Edit the service details by changing any of the following fields:
 - **Name**
 - **Port** - Each core service has two ports, SSL and non-SSL. For trusted connections, you must use the SSL port.
 - **SSL** - For trusted connections, you must use SSL.
 - **Username and Password** - Use these credentials to test the connection to a service.
 - a. If you use a trusted connection, delete the username.
If you do not use a trusted connection, type a username and password.
 - b. Click **Test Connection**.
3. Click **Save**.

Delete a Service

1. In the Services view, select one or more services and click  or  > **Delete**.
2. A dialog requests confirmation. To delete the service, click **Yes**.

The deleted service is no longer available to the NetWitness Platform modules.

Explore and Edit Service Property Tree


You have advanced access and control of service functionality in the Services Explore view, which consists of two parts. The Node list displays service functionality in a tree structure of folders. The Monitor panel displays properties of the folder or file selected in the Nodes list.

Each of the following procedures starts in the Explore view.

To navigate to the Explore view:

1. In NetWitness Platform, go to **ADMIN > Services**.

2. Select a service, then select  > **View > Explore**.
The Explore view is displayed. The Node list is on the left and the Monitor panel is on the right.



Display or Edit a Service Property

To display a service property:

1. Right-click a file in the Node list or Monitor panel.
2. Click **Properties**.

To edit the value of a service property:

1. In the **Monitor** panel, select an editable property value.
2. Type a new value.

Send a Message to a Node


1. In the Properties Dialog, select a **message type**. Options vary according to the file selected in the Node list.
A description of the selected message type is displayed in the **Message Help** field.
2. (Optional) If the message requires them, type the **Parameters**.
3. Click **Send**.
The value or format is displayed in the **Response Output** field.

Terminate a Connection to a Service

You can view sessions that are running on a service in the Service System view. From within the list of sessions, you can terminate the session and terminate active queries in a session.

Terminate a Session on a Service

1. In NetWitness Platform, go to **ADMIN > Services**.
The Admin Services view is displayed.
2. Select a service, and select  > **View > System**.
The Service System view is displayed.



The screenshot shows the NetWitness Platform Admin Services view. The top navigation bar includes RSA, RESPOND, INVESTIGATE, MONITOR, CONFIGURE, and ADMIN. The left sidebar shows Hosts, Services, Event Sources, Health & Wellness, System, and Security. The main content area displays the following information:

Broker Service Information

Name	NW Server (Broker)
Version	11.2.0.0 (Rev null)
Memory Usage	38376 KB (0.03% of 126 GB)
CPU	0%
Running Since	2018-May-22 13:51:43
Uptime	1 week 1 day 4 hours 14 minutes
Current Time	2018-May-30 18:05:43

Appliance Service Information

Name	NW Server (Host)
Version	11.2.0.0 (Rev null)
Memory Usage	23076 KB (0.02% of 126 GB)
CPU	0%
Running Since	2018-May-22 13:51:43
Uptime	1 week 1 day 4 hours 13 minutes 59 seconds
Current Time	2018-May-30 18:05:42

Broker User Information

Name	admin
Groups	Administrators
Roles	aggregate, concentrator.manage, connections.manage, index.manage, logs.manage, sdk.content, sdk.manage, sdk.meta, sdk.packets, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage

Host User Information

Name	admin
Groups	Administrators
Roles	appliance.manage, connections.manage, logs.manage, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage

Session Information


Session	User	IP Address	Login Time	Active Queries
315	admin	IP Address	2018-May-22 13:51:51	0
342	admin	IP Address	2018-May-22 13:51:52	0
381	escalateduser	IP Address	2018-May-22 13:52:43	0
31612	escalateduser	IP Address	2018-May-30 18:04:38	0

3. In the **Session Information** grid at the bottom, click a *session-number*.
The confirmation dialog is displayed.
4. Click **Yes**.

Terminate an Active Query in a Session

1. Scroll down to the **Sessions** grid.
2. In the **Active Queries** column, click a non-zero count of active queries for a session. You cannot click on it if there are 0 active queries.

The Active Queries dialog is displayed.



3. Select a query and click **Cancel Query**.
The query stops and the Active Queries column is updated.

Search for Services

You can search for services from the list of services in the Services view. The Services view enables you to quickly filter the list of services by Name, Host, and Service Type. You can use the Filter drop-down menu and the Filter field separately or at the same time to filter the Services view.

Search for a Service

1. In NetWitness Platform, go to **ADMIN> Services**.
2. In the **Services** panel toolbar, type a service **Name** or **Host** in the **Filter** field.




The Services panel lists the services that match the names entered in the Filter field. The following example shows the search results after starting to type **log** in the filter field.

Services						
Licenses log						
☐	Name	Licensed	Host	Type	Version	Actions
☐	 Log Collector	 	Log Decoder	Log Collector	11.2.0...	
☐	 Log Decoder	 	Log Decoder	Log Decoder	11.2.0...	
« < Page 1 of 1 > » ↻ Displaying 1 - 2 of 2						

Filter Services by Type

1. In NetWitness Platform, go to **ADMIN > Services**.
2. In the Services view, click  and select the service types that you want to appear in the Services view.



The selected service types appear in the Services view. The following example shows the Services view filtered for Concentrator and Log Decoder.

Services

☐	Name	Licensed	Host	Type	Ver	Actions
☐	Concentrator	✓	Concentrator	Concentrator	11	
☐	Concentrator	✓	EndpointLogHybrid	Concentrator	11	
☐	Log Decoder	✓	EndpointLogHybrid	Log Decoder	11	
☐	Log Decoder	✓	Log Decoder	Log Decoder	11	
☐	Concentrator	✓	LogHybrid	Concentrator	11	
☐	Log Decoder	✓	LogHybrid	Log Decoder	11	
☐	Concentrator	✓	NetworkHybrid	Concentrator	11	

Filter

- ☐ Admin Server
- ☐ Archiver
- ☐ Broker
- ☐ Cloud Gateway Server
- ☒ Concentrator
- ☐ Config Server
- ☐ Content Server
- ☐ Contexthub Server
- ☐ Decoder
- ☐ Endpoint Server
- ☐ Entity Behavior Analytics
- ☐ Event Stream Analysis
- ☐ Integration Server
- ☐ Investigate Server
- ☐ Log Collector
- ☒ Log Decoder
- ☐ Malware Analysis
- ☐ Orchestration Server
- ☐ Reporting Engine
- ☐ Respond Server
- ☐ Security Server
- ☐ Source Server
- ☐ UEBA Server
- ☐ Warehouse Connector
- ☐ Workbench

Page 1 of 1

Find the Services on a Host

In addition to being able to locate the services for a host in the Services view, you can also quickly find the services that run on a host in the Hosts view.

1. In NetWitness Platform, go to **ADMIN > Hosts**.
2. In the Hosts view, select a host and click the box that contains a number (the number of services) in the **Services** column.
A list of the services on the selected host is displayed.

In the following example, a list of four services on the selected host are listed after clicking the box containing the number 4.

The screenshot shows the NetWitness Platform interface. The top navigation bar includes tabs for RESPOND, INVESTIGATE, MONITOR, CONFIGURE, and ADMIN. The ADMIN tab is selected, and the Hosts view is active. The Hosts table lists various hosts with columns for Name, Host, Services, Current Version, Update Version, and Status. A dropdown menu is open for the host 'NW Server (co-located Broker)', showing a list of services: Concentrator, Endpoint Server, Log Collector, and Log Decoder.

Name	Host	Services	Current Version	Update Version	Status
☐ NW Server (co-located Broker)	IP-address	10	11.2.0.0		Up-to-Date
☐ Archiver	IP-address	2	11.2.0.0		Up-to-Date
☐ Concentrator	IP-address	1	11.2.0.0		Up-to-Date
☐ Endpoint Log Hybrid	IP-address				Up-to-Date
☐ Event Stream Analysis Primary	IP-address				Up-to-Date
☐ Log Decoder	IP-address				Up-to-Date
☐ Log Hybrid	IP-address				Up-to-Date
☐ Malware Analysis	IP-address				Up-to-Date
☐ Network Decoder (Packets)	IP-address	1	11.2.0.0		Up-to-Date
☐ Network Hybrid (Packets)	IP-address	2	11.2.0.0		Up-to-Date

The dropdown menu for the 'NW Server (co-located Broker)' host shows the following services:

- Concentrator
- Endpoint Server
- Log Collector
- Log Decoder

3. You can click the service links to view the services in the Services view.

Start, Stop, or Restart a Service

These procedures apply to core services only.

Each of the following procedures starts in the Services view. In NetWitness Platform, go to **ADMIN > Services**.

Start a Service

Select a service and click  > **Start**.

Stop a Service

When you stop a service, all of its processes stop and active users are disconnected from it.

To stop a service:

1. Select a service and click  > **Stop**.
2. A dialog requests confirmation. To stop the service, click **Yes**.

Restart a Service

Occasionally, you have to restart a service for changes to take effect. When you change a parameter that requires a restart, NetWitness Platform displays a message.


To restart a service:

1. Select a service and click  > **Restart**.
2. A dialog requests confirmation. To stop the service, click **Yes**.

The service stops, then restarts automatically.

View Service Details

You can view and edit information about services using options in the View menu for a service.



Purpose of Each Service View

Each view displays a functional piece of a service and is described in detail in its own section:

- System View shows a summary of service, appliance service, host user, and session information.
- Services Stats View provides a way to monitor service operations and status.
- Services Config View is for configuring all aspects of a service.
- Services Explore View is for viewing and editing host and service configurations.
- System Logging Panel shows service logs that you can search.
- Services Security View is a way to add NetWitness Platform Core user accounts for aggregation, thick client users, and REST API users.


Access a Service View

To access a view for a service:

1. In NetWitness Platform, go to **ADMIN > Services**.

2. Select a service and click  > **View**.

The View menu is displayed.




3. From the options on the left, select a view.

This is a System view for a Broker.


Session	User	IP Address	Login Time	Active Queries
315	admin	IP Address	2018-May-22 13:51:51	0
342	admin	IP Address	2018-May-22 13:51:52	0
381	escalateduser	IP Address	2018-May-22 13:52:43	0
31612	escalateduser	IP Address	2018-May-30 18:04:38	0

4. Use the toolbar to navigate:



- a. Click **Change Service** to select another service.
The **Administrative Service** dialog is displayed.

- b. Select the checkbox to the left of the service that you want.
- c. Select the view that you want for the service you selected in the View drop-down menu.



The new view (for example, Stats) is displayed for the service you selected.

Hosts and Services Views References

This topic is a reference for features in the NetWitness Platform ADMIN user interface.

This topic describes features available in the NetWitness Platform Admin user interface. The Admin module pulls NetWitness Platform Admin activities into a single view to monitor and manage hosts (appliances), services, tasks, and security.

Topics

- [Hosts View](#)
- [Services View](#)
- [Services Config View](#)
- [Services Explore View](#)
- [Services Logs View](#)
- [Services Security View](#)
- [Services Stats View](#)

Hosts View

You set up and maintain the physical or virtual machine on which NetWitness Platform services run in the **Hosts** view.

IMPORTANT: For help on resolving errors you receive during version installation and update, see [Troubleshooting Version Installations and Updates](#).

A service performs a unique function, such as collecting logs or archiving data. Each service runs on a dedicated port and is modeled as a plug-in to enable or disable, according to the function of the host. You must configure the Core services first.


Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Admin	N/A	N/A	Implemented with the NW Server
Archiver	50008	56008	
Broker	50003	56003	Core Service
Cloud Gateway	N/A	N/A	
Concentrator	50005	56005	Core Service
Config	N/A	N/A	Implemented with the NW Server.
Content	N/A	N/A	Implemented with the NW Server
Context Hub	N/A	N/A	
Decoder (Packets)	50004	56004	Core Service
Endpoint	N/A	N/A	
Entity Behavior Analysis	N/A	N/A	
Event Stream Analysis	N/A	50030	
Integration	N/A	N/A	Implemented with the NW Server.
Investigate	N/A	N/A	Implemented with the NW Server.
Log Collector	50001	56001	
Log Decoder	50002	56002	Core Service
Malware Analysis	N/A	60007	
Orchestration	N/A	N/A	Implemented with the NW Server.
Reporting Engine	N/A	51113	Implemented with the NW Server.
Respond	N/A	N/A	Implemented with the NW Server.

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Security	N/A	N/A	Implemented with the NW Server.
Source	N/A	N/A	Implemented with the NW Server
UEBA	N/A	N/A	
Warehouse Connector	50020	56020	
Workbench	50007	56007	

You must configure hosts and services to communicate with the network and each other so they can perform their functions such as storing or capturing data.

Workflow

This workflow shows the procedures you complete to set up a host, maintain a host, and update the host with new NetWitness Platform versions. Setting up a host is the first task in this workflow. The hosts with core services are set up out-of-the-box. After that, you can set up additional hosts to enhance your NetWitness Platform deployment. The other two tasks, maintaining a host and updating versions for a host, are performed when required and do not have a specific order of completion.




What do you want to do?

For detailed instructions of the following tasks, see [Hosts and Services Procedures](#).

Role	I want to ...
Administrator	Setup up a host.
Administrator	Maintain a host.
Administrator	Apply version updates to a host.

* You can perform these tasks in the current view.

Quick Look



The following example shows you how to set up a host.

- 1 Select **ADMIN > Hosts**.
- 2 Select the host you deployed (for example, **Event Stream Analysis Primary**).
- 3 Click  **Install** (Install icon).
- 4 Select the host type to install from the **Install Services** dialog (for example, **ESA Primary**). This host type installs the Entity behavior Analytics, Context Hub, and Event Stream Analysis services on this host.



Hosts Panel Toolbar

The Hosts view toolbar contains the tools that you use to maintain the hosts in your NetWitness Platform deployment.

In NetWitness Platform, go to **Admin > Hosts** to access the Hosts view. The Hosts panel toolbar is at the top of the Hosts grid in the Hosts view.

Features

The following table describes the features of the Hosts panel toolbar.

Features	Description
	Remove From Group: If the host is part of a host group, you can remove the host from the group.
	Open the Edit Host dialog in which you edit a host or service identification and basic communication settings. This dialog has the same features as the Add Host dialog. Related procedure: Step 1. Deploy a Host
	Opens the Install Services dialog from which you can install a service on a deployed host. Related procedures: Step 2. Install a Service on a Host
	• Update - Updates the host or hosts you have selected with the version you select in the Update Version column. • Check for Updates - Checks the Local Update Repo for the latest updates available from RSA. Related procedure: Apply Version Updates to a Host
	Most of the time, the Discovery function completes automatically and you do not need to click Discover. For a fresh installation, click Discover to access the Provision dialog box so you can complete the provisioning phase. After the provisioning phase, NetWitness Platform automatically discovers services running on the host and you do not need to click Discover. For a fresh installation, click Discover to access the Provision dialog box so you can complete the provisioning phase. After the provisioning phase, NetWitness Platform automatically discovers services running on the host.
	Restart the host.
Filter	Filter hosts by Name or Host.

Groups Panel Toolbar

The Groups panel toolbar provides options for managing groups of hosts. Use the toolbar to create, edit, and delete groups. After you create a group, you can drag individual hosts from the Hosts panel into that group.

Use groups may to organize hosts by function, geography, project, or any other organization principle that is useful. A host may belong to more than one group.

In NetWitness Platform, go to **ADMIN > Hosts**. The Groups panel toolbar is at the top of the Groups grid in the Hosts view.

The Groups panel provides a way to create logical groups of hosts. Once hosts are grouped, it is easier to perform operations on multiple hosts by interacting with each host in a group rather than individual hosts from a non-grouped list.

Note: In NetWitness Live, groups can subscribe to resources while individual hosts cannot.

The Groups panel consists of a grid populated with a list of defined host groups and the Groups Panel Toolbar.

Column	Description
	Displays a new row in the Group grid in which you enter the name of a new group.
	Asks for confirmation that you want to delete the group or host. You can confirm or cancel the deletion.
	Opens the name field in a row of the Group grid so that you can type a new name for an existing group.
	Refreshes the selected group.
Name	The name of the host group. Click the group name to list the hosts in that group on the Hosts panel.
<Blank>	Indicates the number of hosts in the group. Click the number of hosts in the group to list the hosts in that group on the Hosts panel.

Services View

You set up and maintain the NetWitness Platform services run in the **Services** view. With the Services view, you can:

- Quickly search for and locate a specific service or type of service, such as Log Decoder or Warehouse Connector
- Use shortcuts to get to administration tasks
- Add, edit, and remove services
- Sort services by name and host
- Filter services by type and by name and host
- Start, stop, and restart services

A service performs a unique function, such as collecting logs or archiving data. Each service runs on a dedicated port and is modeled as a plug-in to enable or disable, according to the function of the host. You must configure the following Core services first.


Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Admin	N/A	N/A	Implemented with the NW Server
Archiver	50008	56008	
Broker	50003	56003	Core Service
Cloud Gateway	N/A	N/A	
Concentrator	50005	56005	Core Service
Config	N/A	N/A	Implemented with the NW Server.
Content	N/A	N/A	Implemented with the NW Server
Context Hub	N/A	N/A	
Decoder (Packets)	50004	56004	Core Service
Endpoint	N/A	N/A	
Entity Behavior Analysis	N/A	N/A	
Event Stream Analysis	N/A	50030	
Integration	N/A	N/A	Implemented with the NW Server.
Investigate	N/A	N/A	Implemented with the NW Server.
Log Collector	50001	56001	
Log Decoder	50002	56002	Core Service

Service	Unencrypted Non-SSL Port	Encrypted SSL Port	Notes
Malware Analysis	N/A	60007	
Orchestration	N/A	N/A	Implemented with the NW Server.
Reporting Engine	N/A	51113	Implemented with the NW Server.
Respond	N/A	N/A	Implemented with the NW Server.
Security	N/A	N/A	Implemented with the NW Server.
Source	N/A	N/A	Implemented with the NW Server
UEBA	N/A	N/A	
Warehouse Connector	50020	56020	
Workbench	50007	56007	

You must configure hosts and services to communicate with the network and each other so they can perform their functions such as storing or capturing data.

Workflow

This workflow shows the procedures you complete to set up and maintain a service. Adding a service to a host is the first task in this workflow. The hosts with core services are set up out-of-the-box. After that, you can set up additional services on hosts to enhance your NetWitness Platform deployment.



What do you want to do?

See [Hosts and Services Procedures](#) for detailed instructions of the following tasks.


Role	I want to ...
Administrator	Maintain a service.
Administrator	Set up a host.

Related Topic

- [Troubleshooting Version Installations and Updates](#)

Quick Look

The following example shows you how to maintain a service.



Select a Service.

- 1 Go to **ADMIN > Services** view.
- 2 Click the checkbox to the left of the service you want to select.

Edit the Service Name and Connection.

- 3 Click  (Alternatively, select Edit from the  (Action drop-down menu).
- 4 Edit the **Host** name.
- 5 Edit the **Port** number.
- 6 Deselect or select SSL communication connection.
- 7 Click **Test Connection**.
- 8 Click Save.

Delete a Service.

- 9 **Select a Service** and click the delete icon.

View Service Statistics and Configure Parameters

- 10 Perform the following steps to view service statistics and configure a service parameters.
 - a. **Select a Service** and click the actions icon.
 - b. Click **View** and select:
 - **System** to:
 - View current high-level information about the service and its host.
 - Access the System View toolbar.
 - **Stats** to view detailed service statistics.
 - **Config** to view and configure service parameters.
 - **Explore** to view and configure service parameters in the NetWitness Platform Explore view.
 - **Logs** to view log messages issued by the service.

- 11 **Select a Service**, click the actions icon, and click **Stop** a service that is running.

- 12 **Select a Service**, click the actions icon, and click **Restart** to restart a stopped service.

Topics

See the following RSA NetWitness Platform guides for detailed information on individual services. Go to the [Master Table of Contents](#) to find all NetWitness Platform Logs & Network 11.x documents.

Archiver Configuration Guide

Broker and Concentrator Configuration Guide

Cloud Behavioral Analytics Gateway Configuration Guide

Context Hub Configuration Guide

Decoder and Log Decoder Configuration Guide

Endpoint Insights Configuration Guide

Event Stream Analysis (ESA) Configuration Guide

Investigate and Malware Analysis User Guide

Log Collection Configuration Guide

Malware Analysis Configuration Guide

Reporting Engine User Guide

Respond Configuration Guide

RSA NetWitness UEBA User Guide

Workbench Configuration Guide


Warehouse Connector Configuration Guide

Edit Service Dialog

This topic introduces the Edit Service dialog accessible from the ADMIN Services view (ADMIN > Services).

NetWitness Platform services are automatically discovered in NetWitness Platform.

You can use the Edit Service dialog to modify services. To access the Edit Service dialog, go to **ADMIN > Services** and click  in the **Services** panel toolbar.



Procedures related to services are described in [Hosts and Services Procedures](#).

Features

This table describes the features of the Add Service or Edit Service dialogs.

Field or Option	Description
Service	Displays the service type. You can add the following services: Archiver, Broker, Concentrator, Decoder, Event Stream Analysis, Incident Management, IPDB Extractor, Log Collector, Log Decoder, Malware Analysis, Reporting Engine, Warehouse Connector, and Workbench.
Host	Specifies the host on which the service resides.
Name	Specifies the name used to identify the service; for example, Broker . An understandable naming convention can make administrative tasks easier. Some administrators find it convenient to use the hostname or IP address (specified in the Host field) for the Name as well.
Port	Specifies the port used to communicate with this service. The default port based on the selected service type in the Service field is autofilled here. If you select SSL below, this port becomes an SSL port. If you do not select SSL , it becomes a non-SSL port. You can customize this port by opening a firewall for the port that you add. For information on ports, see the Network Architecture and Ports topic in the <i>Deployment Guide</i> .
SSL	Indicates that NetWitness Platform uses SSL for communications with this service.

Field or Option	Description
Username	Specifies the user name used to log in to this service. The default username is admin .
Password	Specifies the password used to log in to this service. The default password is netwitness .
Test Connection	Tests the connection of a service that you are adding.
Cancel	Closes the Add Service or Edit Service dialog. If you do not save the service before closing the dialog, the service is not added or edited.
Save	Saves the new service.

Groups Panel Toolbar

This topic introduces the features and options in **ADMIN > Services** view > **Groups** panel toolbar.

The Groups panel toolbar provides options for managing groups of services. The toolbar includes options to create, edit, and delete groups. After you create a group, you can drag individual services from the Services panel into the group.

Groups may reflect functional, geographical, project-oriented, or any other organization principle that is useful. A service may belong to more than one group.

To access the Services view, in **NetWitness Platform**, go to **ADMIN > Services**. The Groups panel toolbar is at the top of the Groups grid in the Services view.

Features

This table describes toolbar features.

Option	Description
	Displays a new row in the Group grid in which you enter the name of a new group.
	Asks for confirmation that you want to delete the group or service. You can confirm or cancel the deletion.
	Opens the name field in a row of the Group grid so that you can type a new name for an existing group.
	Refreshes the selected group.

Services Panel Toolbar

This topic introduces the options in Service panel toolbar to add, remove, edit, and get a license for services. You can also filter the services listed in the Services Panel.

To access the Administration Services view, in **NetWitness Platform**, go to **ADMIN > Services**. The Services panel toolbar is at the top of the Services grid in the Services view.

Features

The table describes the features of the Services panel toolbar.

Feature	Description
	Adds a service for this instance of RSA NetWitness Platform to manage (see Step 2. Install a Service on a Host).
	Deletes a service from this instance of NetWitness Platform (see Edit or Delete a Service).
	Edits service identification and basic communication settings.
 Filter	Filters the services listed in Services view. In the Filter drop-down menu, you can filter the services by one or more selected service types. In this example, when you select Concentrator and Decoder, only the Concentrator and Decoder services appear in the Services view. In the Filter field, you can filter the services by Name and Host. You can use the Filter drop-down menu and the Filter field at the same time to filter the services listed in the Services view.

Services Config View

This topic introduces the features and functions of the Services Config view.


The Services Config view is one of the views available from the **Services** > Actions () menu. It provides a user interface for configuring all aspects of a core service or NetWitness Platform service.

The configuration options in the Services Config view are organized as tabs, with each tab providing a view of a set of related parameters. Unlike the Services Explore view, which offers direct access to all configuration files for a service, these tabs present the most commonly modified parameters of service configuration in a user-friendly view.

Due to configuration requirements for different services; each type of service has variations in available tabs and configuration parameters in this view. Individual topics describe configuration parameters that are specific to a host (Brokers and Concentrators, Decoders and Log Decoders) or service (for example, Reporting Engine, IPDB Extractor, Log Collector, and Warehouse Connector).

Workflows

The following workflow shows the configuration tasks for the Decoder service as an example of this view. For details on their **ADMIN** > **Services** > **Config** views, see the individual service Configuration Guides (for example, the *RSA NetWitness® Platform Broker and Concentrator Configuration Guide*) .



To access the Services Config view:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
The Administration Services view is displayed.
2. Select a service and select  > **View > Config**.
Services Config view for the selected service is displayed.

Quick Look

This is an example of the Services Config view for a Decoder.

System Configuration

Name	Config Value
Compression	0
Port	50004
SSL FIPS Mode	☒
SSL Port	56004
Stat Update Interval	1000
Threads	20

Decoder Configuration

Name	Config Value
Adapter	
Berkeley Packet Filter	
Capture Interface Selected	packet_mmap_lo (bpf)
Cache	
Cache Directory	/var/netwitness/decoder/cache
Cache Size	4 GB
Capture Settings	
Assembler Maximum Size	32 MB
Assembler Minimum Size	0

Parsers Configuration Enable All Disable All

Specify if relevant meta data is generated to disk (Enabled), generated only in memory for other Decoder content use (Transient), or not generated at all (Disabled).

Name	Config Value
ALERTS	Enabled
DHCP	Enabled
DNS	Enabled
Entropy	Disabled
FeedParser	Enabled
fingerprint_office_lua	Enabled
fingerprint_pdf_lua	Enabled
fingerprint_rar_lua	Enabled
fingerprint_rtf_lua	Enabled
fingerprint_zip	Enabled
FTP	Enabled
GeoIP	Disabled
GeoIP2	Mixed
GTalk	Enabled
H323	Enabled
HTTP	Enabled

Apply

This is an example of the Services Config view for a Concentrator.

Aggregate Services

+ - ✎ ⚙ Edit Service | ⏻ Toggle Service | ▶ Start Aggregation | ⏻ Stop Aggregation

☐	Address	Port	Rate	Max	Behind	Meta Field	Filter	Meta Includ	Grouped	Status
☐	Ip-address	56..	0	186	0				no	consumi
☐	Ip-address	56..	0	24...	0				no	consumi

System Configuration

Name	Config Value
Compression	0
Port	50005
SSL FIPS Mode	☒
SSL Port	56005
Stat Update Interval	1000
Threads	20

Aggregation Configuration

Name	Config Value
Aggregation Settings	
Aggregate Autostart	☐
Aggregate Hours	0
Aggregate Interval	10
Aggregate Max Sessions	10000
Service Heartbeat	
Heartbeat Error Restart	300
Heartbeat Next Attempt	60
Heartbeat No Response	180

Apply

Topics

- [Topic](#)
- [Features](#)
- [Edit a Service Configuration File](#)

Appliance Service Configuration Tab


This topic lists and describes the available configuration parameters for the NetWitness Platform Core Appliance service. The NetWitness Platform Core Appliance service provides hardware monitoring on legacy NetWitness hardware.

The Configuration view for the Archiver, Broker, Concentrator, IPDB Extractor, Decoder, Log Collector, or Log Decoder service has an Appliance Service Configuration tab.

To access the Appliance Service Configuration tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
The Administration Services view is displayed.
2. Select a service and select  > **View > Config**.
Services Config view for the Archiver service is displayed.
3. Click the **Appliance Service Configuration** tab.

This is an example of the Appliance Service Configuration tab for an Archiver.



Name	Config Value
Compression	0
Port	50006
SSL FIPS Mode	☒
SSL Port	56006
Stat Update Interval	1000
Threads	20

Apply

Name	Description of Configuration Value	When Changes Take Effect
Compression	Compresses a message when it reaches the positive number (in bytes) that you specify.	The next time you connect to this service.

Name	Description of Configuration Value	When Changes Take Effect
Port	Unencrypted listening port. 0 indicates that the port is disabled.	Upon restart of the service.
SSL FIPS Mode	One of the parameters you need to enable or disable Federal Information Processing Standards (FIPS). For detailed instructions, see "Activate or Deactivate FIPS" in the <i>RSA NetWitness® Platform System Maintenance Guide</i> .	Upon restart of the service.
SSL Port	SSL (Secure Sockets Layer) listening port. 0 indicates that the port is disabled. SSL is the standard security technology for establishing an encrypted link between a web server and a browser. This link ensures that all data passed between the web server and browsers remain private and integral.	Upon restart of the service.
Stat Update Interval	How often (in milliseconds) the system updates statistic nodes for monitoring Health and Wellness.	Immediately.
Threads	Threads in thread pool required to used to handle requests. The Threads parameter works with the Polling Interval parameter for event and log threads.	Immediately.

Topic

Appliance Service Configuration Parameters

Data Retention Scheduler Tab

This topic describes the configurable options in the Data Retention Scheduler tab for Decoder, Log Decoder, and Concentrator.

In the Data Retention Scheduler tab, you can define the criteria for removing database records from primary storage on Decoder, Log Decoder, and Concentrator services, and schedule the timing for checking the threshold.


For information on the Data Retention tab for Archiver, see the **Data Retention Tab - Archiver** topic in the *Archiver Configuration Guide*.

Note: If additional customization is necessary, use the Scheduler under the Files tab in the Services Config view. For example, if you have storage available to save the RAW data versus the meta, use Capacity as the threshold and to set different thresholds per database (meta versus packet).

To access the Data Retention Scheduler tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a Decoder, Log Decoder, or Concentrator, and then select  > **View > Config**.
3. In the **Services Config** view for the service, click the **Data Retention Scheduler** tab.

The following figure illustrates the parameters in the Data Retention Scheduler tab for a Concentrator.



Features

The Data Retention Scheduler tab has sections to specify Threshold settings and Run settings. The following table lists the parameters supported for data retention configuration.

Parameter	Description
Threshold	The threshold is based on the age of the data, the amount of time the data was stored or the date on which the data was stored. The date is from the database file, not from the actual session time. • Duration: The duration of time that data can be stored before removal. Specifies the number of days (365 maximum), hours (24 maximum), and minutes (60 maximum) that have elapsed since the time stamp on the data. • Date: The removal of data based on the date of the timestamp. Specifies the monthly date and time in the Calendar and Time fields.

Parameter	Description
Run	The schedule for running the job that checks rollover criteria. • Interval: Schedule the database check to occur at a regular interval. Specifies the Hours and Minutes between the scheduled checks. • Date and Time: Schedule the database check to occur at a regular day and time. Specifies the day from the drop-down list and the system clock time in hh:mm:ss format. Possible values for day are Everyday, Weekdays, Weekends, and Custom, where Custom allows you to select one or more specific days of the week.
Apply	Overwrites any previous schedule for this service and applies the new settings immediately. Caution: After you apply these settings, when the threshold is met the system deletes the old data from the database and you can no longer access it.
Reset	Resets the schedule to the last applied state.

Files Tab

This topic describes the service configuration files that are visible in the Services Config view > Files tab.

Use the Files tab in the Services Config view to edit service configuration files for Decoders, Log Decoders, Brokers, Archivers, and Concentrators as text files.

The files you can edit vary depending upon the type of service you are configuring. The following files are common to all core services.

- service index file
- netwitness file
- crash reporter file
- scheduler file
- feed definitions file

In addition, the Decoder has files that configure parsers, feed definitions, and a wireless LAN adapter.

Note: The default values in the configuration files cover most common situations. You may need to edit configuration parameters and values for optional services, such as the crash reporter or scheduler. Do not change these values in the Files tab unless you understand networks and the factors that affect the way services collect and parse data.


More detail on the service configuration parameters is available in the [Service Configuration Settings](#).

To access the Files tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service and select  > **View > Config**.
The Services Config view is displayed with the **General** tab open.
3. Click the **Files** tab.


Edit a Service Configuration File

This is an example of the Files tab.



Files Tab Toolbar

The Files tab has a toolbar and an edit window. This is an example of the toolbar.



These are the features of the Files tab toolbar.

Feature	Description
File drop-down list	Displays a list of files that the system is currently using. When you select a file, the text of the file is displayed in the text edit window. In the text window, you can edit the file and save the changes, or create alternate files to use.
Service / Host drop-down list	Displays the service type and host. You can open a file from either the service or the host for editing.

Feature	Description
 Get Backup	Retrieves the latest backup of the current file, which can prove useful when you have made changes and want to go back to the previous version of the file. The backup does not replace the current file unless you click Save .
 Push	Displays a dialog in which you can select services of the same type and push the currently viewed file to the services.
Apply	Overwrites the current file, creates a backup file.

Services Explore View

Use the NetWitness Platform Services Explore view, to display and edit host and service configurations.

The Services Explore View offers advanced access and control of all NetWitness Platform hosts and services. All services expose their functionality through a tree-like series of nodes, similar to the Windows Explorer view of your file system. Here you can:


- View a directory tree showing common files for all selected services.
- Navigate down through the directory to a file.
- Open the same file for each service, and display the contents side by side.
- Select an entry in the file and edit the value.
- Apply a property value from one service to other services.

The Services Explore View can also display a Properties dialog, a simple interface for viewing properties of any node in the system and sending messages to the node, shown in the figure below.

Caution: A good understanding of the nodes and parameters is required when editing in this view. Incorrect settings can cause performance problems.

Workflow


This workflow shows the tasks you perform from the Explore view.



Quick Look

To access the Services Explore view:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service and select  > **View > Explore**.



- 1 Expand the node to display its parameter categories.
- 2 Click a property (for example, **meta.dir**) to select it.
- 3 Right-click a node or category and click **Properties** to display the Properties dialog.
- 4 Perform an operation on a node or category:
 - a. Select a command from the drop-down list.
 - b. Enter a command string (if required).
 - c. Click **Send**.
- 5 Review the output.

Features


The **Services Explore View** has two main panels:

- The Node list
- The Monitor panel

Right-click a file and select Properties to access it.

The Node List

The Node list displays the services as a tree-like series of nodes and folders. The levels in the Node list expand and collapse to display the full hierarchy.



Each root folder is named based on the functionality it exposes. For instance, the **/connections** folder shows all connected IP addresses. Underneath each **IP/Port** are two folders, **sessions** and **stats**.

- The **sessions** folder displays all authenticated user sessions originating from the IP/Port.
- The **stats** folder displays values, such as the number of messages sent/received, bytes sent/received, and others, set by the service. These are not editable.

Selecting any folder in the tree view displays its children in the **Monitor** panel. Every node in the tree is actively monitored, so when a statistic or configuration node changes value, it is immediately reflected in the tree and monitor panel.

The Monitor Panel

The **Monitor** panel displays properties and values for a selected node (such as **index**) and a child folder (such as **config**). There are two ways to edit values:

- Click the value and type a new value
- Send a **set** message in the Properties dialog

/Index/Config	(Concentrator)
index.dir	/var/netwitness/concentrator/index=7.08 GB
index.dir.cold	
index.dir.warm	
page.compression	huffhybrid
save.session.count	0

Topics

- [Features](#)
- [Log Decoder Service Configuration Parameters](#)

Properties Dialog

Use the Services Explore view > Properties dialog to perform the following tasks.

- Send messages to a system node
- Retrieve values for a property for multiple services
- Set values for a property for multiple services

When you select Properties from the context menu, the Properties dialog opens below the Monitor panel .


All nodes support have help that contains the following information.

- A description of the node
- The list of supported messages with a corresponding description
- Security roles needed to access the messages

The available messages vary according to the service and root folder. Many of these messages are also accessible as options with a NetWitness Platform dashboard or view.


To access the Properties dialog:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service and select  > **View > Explore**.
3. In the **Node** list, select a file.
4. In the **Monitor** panel, right-click a property and select **Properties**.



The Properties dialog is displayed. You can also right-click any file in the Node list to display the Properties dialog.

The following example shows the Properties dialog with help for a message (**info**) displayed.



Features

The Properties dialog has the following features.

Feature	Description
Message drop-down list	Lists all available messages for the current node. Select a message to send the node.
Parameters input field	Type the message parameters in this field.
Send button	Sends the message to the node.
Message Help	Displays help text for the current message.
Response Output	Displays the response to a message or output from a message.

Services Logs View

This topic introduces the Services Logs view.

The Services Logs view provides the ability to view and search the logs for a specific service. The Services Logs view is identical to the System Logging Panel with two exceptions:


- The Services Logs view has an additional filter to select messages for the service or host.
- The System Logging panel has an additional tab for Settings.

For a complete description of NetWitness Platform logging features, see the **ADMIN > System > System Logging** panel.

To view a service log:


1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service and select  **>View > Logs**.

The following figure shows the Services Logs view Realtime tab.



Timestamp	Level	Message
2018-06-05T15:20:59.000	AUDIT	User admin (session 8680, IP address) has finished query (channel 8700, queued 00:00:00, execute 00:00:00): query="select s...
2018-06-05T15:21:03.000	DEBUG	IP address has received a ping command, a reply of 6 bytes was sent
2018-06-05T15:21:16.000	DEBUG	IP address has received a ping command, a reply of 6 bytes was sent
2018-06-05T15:21:59.000	AUDIT	User admin (session 8680, IP address) has issued query (channel 8700) (thread 171074): query="select sessionid, time, refere...
2018-06-05T15:21:59.000	AUDIT	User admin (session 8680, IP address) has finished query (channel 8700, queued 00:00:00, execute 00:00:00): query="select s...
2018-06-05T15:22:03.000	DEBUG	IP address has received a ping command, a reply of 6 bytes was sent
2018-06-05T15:22:16.000	DEBUG	IP address has received a ping command, a reply of 6 bytes was sent
2018-06-05T15:22:37.000	INFO	Accepting connection from trusted peer IP with subject name C = US, ST = VA, L = Reston, O = RSA, OU = NetWitness, CN = 3...
2018-06-05T15:22:37.000	DEBUG	Trusted user admin has been granted QT: 60 ST: 0 QP:

The following figure shows the Services Logs view Historical tab.



Features

The System Logging Panel has the following tabs, and the logging functions are described as part of system maintenance (see **Monitor Health and Wellness of NetWitness Platform** in the *System Maintenance* guide).

Feature	Description
Realtime tab	This is the monitor mode of the service log.
Historical tab	This is a searchable view of the service log.

Services Security View

This topic provides an overview of service security management in the Services Security view.

In NetWitness Platform, each service has a separate configuration of users, roles, and role permissions, which are managed in the Services Security view.

To access service information and perform service operations through NetWitness Platform, a user must belong to a role that has permissions on that service. For 10.4 or later NetWitness Platform Core services that utilize trusted connections, it is no longer necessary to create NetWitness Platform Core user accounts for users that log on through the web client. You only need to create NetWitness Platform Core user accounts for aggregation, thick client users, and REST API users.


Note: Only the default admin user in NetWitness Platform is created by default on all services. As a prerequisite to managing service security, the default admin user account must be present in the NetWitness Platform Administration > Services view. For every other user, you must configure access to each particular service through NetWitness Platform.

Procedures related to this tab are described in [Hosts and Services Procedures](#).

To access the Services Security view:

1. In **NetWitness Platform**, go to **ADMIN > Services**.

2. Select a service and select  > **View > Security**.
The Services Security view for the selected service is displayed.



The screenshot displays the RSA NetWitness Platform interface for the 'Concentrator' service's Security view. The top navigation bar includes tabs for Hosts, Services, Event Sources, Health & Wellness, System, and Security. The 'Services' tab is active, showing a sub-tab for 'Concentrator' and a 'Security' button. The 'Users' tab is selected, showing a list of users on the left and a form for editing a user on the right. The user 'admin' is selected. The form includes fields for Name, Username, Password, Confirm Password, Email, and Description. Below these are 'User Settings' for Auth Type (NetWitness Platform), Query Prefix, Core Query Timeout (60), and Session Threshold (0). At the bottom is a 'Role Membership' section with a list of roles: Groups, Administrators (checked), Aggregation, Analysts, Data_Privacy_Officers, Malware_Analysts, Operators, and SOC_Managers.

Features

The Services Security view has three tabs, Users tab, Roles tab, and Settings tab.

Roles and Service Access

Primary considerations in configuring service security are defining the roles and assigning users to the roles. The Service Security view separates these two functions into the Users tab and the Roles tab.

- In the Roles tab, you can create roles and assign permissions to the roles for a selected service.
- In the Users tab, you can add a user, edit user settings, change the user password, and edit the role membership of the user for a selected service. Although you select a single service in the Services Security view, you can apply the settings for one service to other services.

Topics

- [Roles Tab](#)
- [Service User Roles and Permissions](#)
- [Aggregation Role](#)
- [Settings Tab](#)
- [Users Tab](#)

Roles Tab

This topic introduces the features of the Services Security View > Roles Tab.

The **Roles** tab enables you to create roles and assign permissions. Each role can have different permissions for different services. For example, the Analysts role can have different role permissions based on the selected service.


Before you can add users to roles, you need to define user roles, usually by function, and assign permissions to the roles.

Procedures related to this tab are described in [Hosts and Services Procedures](#).

To display the **Services Security View > Roles** tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service to which you want to add a user, and select  > **View > Security**.
3. Select the **Roles** tab.

The following figure shows the Roles tab in the Services Security view.



Features

The Roles tab has a **Role Name** panel on the left. Selecting a role name shows the **Role Information** panel for the selected role on the right.

Role Name Panel

The **Role Name** panel has the following features.

Feature	Description
	Adds a new group to the current service.
	Deletes the selected group from the current service.
	Copies a role and its assigned permissions to a new role. The name of the new role must be unique. For example, you can copy the Analysts role and create another role with a new name, such as Analyst_Managers .
Replicate	Pushes a role and its assigned permissions to other services. After you select a role and click Replicate , the Replicate Role to other services dialog is displayed. In the dialog, you can select the services where you want to replicate the role.

The following figure shows the **Replicate Role to other services** dialog.

Replicate Role to other services

☐	Name ^	Address	Type
☐	Broker		Broker
☐	Concentrator		Concentrator
☐	Decoder		Decoder
☐			Broker

Cancel

Replicate

Role Information and Permissions Panel

The **Role Information and Permissions** panel defines role permissions.

There are two buttons:

- The **Apply** button saves the changes made in the Role Permissions panel and they become effective immediately.
- If you have not saved changes in the Role Permissions panel, the **Reset** button resets all fields and settings to their values before editing.

Service User Roles and Permissions

This topic describes the pre-configured service user roles and permissions.

The Services Security view Roles tab enables you to create service user roles and assign permissions. You can also use the pre-configured roles included with NetWitness Platform to assign user permissions.

Service User Roles

NetWitness Platform has the following pre-configured service user roles.

Role	Assigned Permissions	Personnel/Account
Administrators	All permissions	NetWitness Platform System Administrator
Aggregation	aggregate sdk.content sdk.meta sdk.packets	You can use this role to create an Aggregation account. This role provides the minimum permissions necessary to perform aggregation of data. It is only available on NetWitness Platform 10.5 and later services.
Analysts, Malware_ Analysts, and SOC_ Managers	sdk.meta sdk.content sdk.packets storedproc.execute	Users can use specific applications, run queries and view content for purposes of analysis.
Data_Privacy_ Officers	sys.manage users.manage sdk.meta sdk.content sdk.packets sdk.manage logs.manage database.manage index.manage dpo.manage	Data Privacy Officer Data Privacy Officers have the dpo.manage permission on Decoders and Log Decoders.
Operators	sys.manage services.manage connections.manage users.manage logs.manage parsers.manage rules.manage database.manage index.manage sdk.manage decoder.manage archiver.manage concentrator.manage storedproc.manage	Operators are responsible for the daily operation of the services.

Service User Permissions

There are many permissions that you can assign a service role in NetWitness Platform. Users can have different permissions on each service, depending on their role assignments and the permissions selected for each role. This table describes the permissions that you can assign to a role.

Permission	Definition
sys.manage	Allows the user to edit the service configuration settings.
services.manage	Allows the user to manage connections to other services.
connections.manage	Allows the user to manage connections to the service.
users.manage	Allows the user to create individual users and user roles and specify user permissions.
aggregate	Allows the user to perform aggregation of data.
sdk.meta	Allows the user to run queries in the Investigation and Reporting applications and to view the metadata returned by the query.
sdk.content	Allows the user to access raw packets and logs from any client application (Investigations and Reporting).
sdk.packets	Allows users to access raw packets and logs from any client application.
appliance.manage	Allows the user to manage the appliance (host) tasks. This permission is required by the Appliance service.
decoder.manage	Allows the user to edit the configuration settings for the Decoder service.
concentrator.manage	Allows the user to edit the configuration settings for the Concentrator/Broker service.
logs.manage	Allows the user to view the service logs and edit the logging configuration settings for the specified service.
parsers.manage	Allows the user to manage all attributes under the parsers node.
rules.manage	Allows the user to add and delete all rules.
database.manage	Allows the user to set database locations, sizes, and the various configuration settings for the session, meta and/or packet/log databases.
index.manage	Allows the user to manage all index-related attributes.
sdk.manage	Allows the user to view and set all SDK configuration items.
storedproc.execute	Allows the user to execute a Lua stored procedure.
storedproc.manage	Allows the user to manage Lua stored procedures.
archiver.manage	Allows the user to modify the Archiver configuration.
dpo.manage	Allows the user to manage the transform configuration and the applicable keys.

Aggregation Role

This topic describes the Aggregation role and permissions that allow service users to perform aggregation.

The Aggregation role is a service user role intended only for aggregation of data. It has the minimum role permissions required to do aggregation:

- aggregate
- sdk.meta
- sdk.packets
- sdk.content


The Aggregation role is available only on NetWitness Platform 10.5 and later services and it can be used for an aggregation account. Members of this role or service users with these permissions can perform aggregation on Decoders, Concentrators, Archivers, and Brokers. The **aggregate** permission allows service users to perform aggregation of sessions and metadata along with raw packets and logs.

You can still use the decoder.manage, concentrator.manage, and archiver.manage permissions, but the Aggregation role permissions allow aggregation only and prevent the other available operations.

You access the service roles from the **ADMIN > Services** (select a service) > **Actions > View > Security > Roles** tab.

Procedures related to roles are described in [Hosts and Services Procedures](#). [Service User Roles and Permissions](#) provides detailed information on the pre-configured roles.


The following figure shows the permissions in the Aggregation role.



Settings Tab

This topic describes the features of the Services Security view > Settings tab.


In the Services Security view Settings tab, Administrators can enable and configure system roles that define permissions on a per meta key basis for individual Brokers, Concentrators, Decoders, and Log Decoders. Configuring this feature adds configurable meta keys to the Services Security view > Roles tab so that individual meta keys can be applied to specific roles on a specific service. The following figure illustrates this.



This configuration is generally part of a data privacy plan implemented to ensure that specific types of content consumed or aggregated by a service are kept secure by limiting visibility of the meta data and content to privileged users (see *Data Privacy Management*).

To display the tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. In the **Services** grid, select a Decoder or Log Decoder service, click  > **View > Security**, and click the **Settings** tab.



Features

The tab includes two features.

Feature	Description
SDK Meta Role Permissions field	Provides option for disabling or configuring meta key and content restrictions. The filtering options are described.
Apply button	Applies the selected configuration immediately. If not disabled, the meta keys are added to the Roles tab so they can be applied to specific roles.

SDK Meta Role Permissions Options

The following table lists the filtering options available in the SDK Meta Role Permissions selection list, and the numeric values used to disable (0) and the types of filtering (1 through 6).

Note: There is no need to know the numeric value unless configuring meta and content visibility manually in the `system.roles` node.

system.roles Node Value	Settings Tab Option	Description
0	No Filtering (Disabled)	System roles that define permissions on a per meta key basis are disabled.
1	Whitelist meta and content	Meta and content for the specified SDK meta roles are white listed, or visible to users assigned the system role.
2	Whitelist only meta	Meta for the specified SDK meta roles is white listed, or visible to users assigned the system role.

system.roles Node Value	Settings Tab Option	Description
3	Whitelist only content	Content for the specified SDK meta roles is white listed, or visible to users assigned the system role.
4	Blacklist meta and content	Meta and content for the specified SDK meta roles are black listed, or not visible to users assigned the system role.
5	Blacklist only meta	Meta for the specified SDK meta roles is black listed, or not visible to users assigned the system role.
6	Blacklist only content	Content for the specified SDK meta roles is black listed, or not visible to users assigned the system role.

Users Tab

This topic explains the features of the Services Security view > Users tab.

In the Services Security view, the Users tab enables you to configure the following for a service:


- Add user accounts.
- Change service user passwords.
- Configure user authentication properties and query handling properties for the service.
- Specify the user role membership, which specifies the roles that the user belongs to on the selected service.

Note: For 10.4 or later NetWitness Platform Core services that utilize trusted connections, it is no longer necessary to create NetWitness Platform Core user accounts for users that log on through the web client. You only need to create NetWitness Platform Core user accounts for aggregation, thick client users, and REST API users.

Procedures related to this tab are described in [Hosts and Services Procedures](#).

To access the Services Security view > Users tab:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
2. Select a service to which you want to add a user, and select  > **View > Security**.



The screenshot shows the NetWitness Platform ADMIN interface. The top navigation bar includes tabs for RESPOND, INVESTIGATE, MONITOR, CONFIGURE, and ADMIN. The ADMIN tab is active, and the 'Services' sub-tab is selected. The 'Concentrator' service is chosen, and the 'Security' view is open. The 'Users' tab is active, showing a 'User List' panel on the left and a 'User Definition' panel on the right. The 'User List' panel contains a table with columns 'Username' and 'Name'. The 'User Definition' panel has three sections: 'User Information' with fields for Name, Username, Password, Email, and Description; 'User Settings' with fields for Auth Type, Core Query Timeout, Query Prefix, and Session Threshold; and 'Role Membership' with a list of roles including Groups, Administrators, Aggregation, Analysts, Data_Privacy_Officers, Malware_Analysts, Operators, and SOC_Managers. The 'Administrators' role is selected.

Features

The Users tab has a User List panel on the left. Selecting a username makes the User Definition panel on the right available.


User List Panel

The User List panel has the following features.

Feature	Description
	Adds a new user to the current service.
	Deletes the selected users from the service.

Feature	Description
	Performs one of the following actions on the selected service user account: • Replicate: Replicates the entire service user account to selected services. • Change Password: Changes the password of a service user and replicates the new password to Core services with that user account defined. The Change Password option replicates only the password change to the Core services selected and does not replicate the entire user account.
Username	The user names for all user accounts that access the service. The username must be one used to log on to NetWitness Platform.

The following figure shows the **Replicate User to other services** dialog.



Replicate User to other services


Please enter and confirm the service user password. The entire service user account replicates to the selected services. The user password also changes on each selected service.

Password

Confirm Password

☐	Name ^	Address	Type
☐	- Broker		Broker
☐	- Conc...		Concentrator
☐	- Archi...		Archiver
☐	- Work...		Workbench
☐	- Log C...		Log Collector
☐	- Log ...		Log Decoder
☐	- Wareh...		Warehouse C...
	NW – Malware A		Malware A

The following figure shows the **Change Password** dialog.



Change Password

Please enter and confirm the service user password. Only the user password changes on the selected services. No other user attributes will replicate to the services

Password

Confirm Password

☐	Name ^	Address	Type
☐	S5EndpointLohHyb - Log Decoder		Log Decoder
☐	S5LogDecoder - Log Collector		Log Collector
☐	S5LogDecoder - Log Decoder		Log Decoder
☐	S5LogHybrid - Concentrator		Concentrator
☐	S5LogHybrid - Log Collector		Log Collector
☐	S5LogHybrid - Log Decoder		Log Decoder
☐	S5MalwareAnalysis - Broker		Broker
☐	S5NWDecoder - Decoder		Decoder
☐	S5PacketHybrid - Concentrator		Concentrator
☐	S5PacketHybrid - Decoder		Decoder
	VLC2514 - Log Collector		Log Collector

Cancel Change Password

User Definition Panel

The User Definition panel has three sections:

- User Information identifies the user as created in the Administration Security view.
- User Settings define parameters that apply to this user's access to the service.
- Role Membership defines user roles to which the user belongs.

There are two buttons:

- The **Save** button saves the changes made in the User Definition panel, and they become effective immediately.
- If you have not saved changes in the User Definition panel, the **Reset** button resets all fields and settings to their values before editing.

User Information

The User Information section has the following features.

Field	Description
Name	The name of the user.

Field	Description
Username	The username that this user enters to log in to the service. This is the NetWitness Platform username generated when the administrator added the user and the associated credentials in the Administration Security view (Administration > Security).
Password (and Confirm Password)	The password that the user enters to log on to the service. This is the NetWitness Platform password generated when the administrator added the user and the associated credentials in the Administration Security view. The NetWitness Platform account password and the service password must match in order to allow the user to connect to the service through NetWitness Platform.
Email	(Optional) The user's email address.
Description	(Optional) A general description field to describe this user.

User Settings

The User Settings section has the following features.

Field	Description
Auth Type	The authentication scheme for this user. The product line supports internal and external authentication. • Netwitness specifies internal authentication, and is enabled by default. In this mode, all users must authenticate with the user account and passwords that are generated when the administrator uses the NetWitness Platform Administration Security view (Administration > Security) to create the user and their associated credentials. • External specifies that authentication is enabled through the host interface with PAM (Pluggable Authentication Modules). For more information, see the Configure PAM Login Capability topic in the <i>System Security and User Management</i> guide.
Query Prefix	(Optional) Always append the query syntax to all queries by this user. For example, adding the query prefix email != 'ceo@company.com' prevents those email results from showing up in the sessions.
SA Core Query Timeout	Note: This field applies to NetWitness Platform 10.5 and later service versions and does not appear for 10.4 and earlier service versions. NetWitness Platform 10.4 and earlier services use Query Level instead of SA Core Query Timeout. Specifies the maximum number of minutes a user can run a query on the service. If this value is set to zero (0), the query timeout is not enforced for the user on the service. When replicating a user from a NetWitness Platform 10.5 or later service to a NetWitness Platform 10.4 service, Query Timeout migrates to Query Level based on the closest level. For example, if a user has a Query Timeout of 15 minutes, the user gets a Query Level of 3 after the migration. If a user has a Query Timeout of 35 minutes, the user gets a Query Level of 2 after the migration. If a user has a Query Timeout of 45 minutes, the user gets a Query Level of 2 after the migration.

Field	Description
Session Threshold	(Optional) Controls the behavior of the application when scanning meta values to determine session counts. Any meta value with a session count that is above the set threshold stops its determination of the true session count when the threshold is reached. If a threshold is set for a session, the Navigation view shows that the threshold was reached and the percentage of query time used to reach the threshold.

Role Membership

The Role Membership section shows the roles that a user is a member of for the selected service.


Services Stats View

This topic describes the features available in NetWitness Platform Services Stats view.

The Services Stats view provides a way to monitor the status and operations of a service. This view displays key statistics, service system information, and host system information for a service. In addition, more than 80 statistics are available for viewing as gauges and in timeline charts. In historical timeline charts, only statistics for session size, sessions, and packets are viewable.

Workflow

This workflow shows the tasks you perform from the Stats view.




In the Stats view, you can customize the monitored statistics for individual services.

The following example shows you how to use the Stats view for a Decoder. The Stats view for all the services provide you with the same information for each service.

To access the Service Stats view:

1. In **NetWitness Platform**, go to **ADMIN > Services**.
The Services view is displayed.
2. Select a service and select  > **View > Stats**.



Features

Although different statistics are available for different types of services, certain elements are common to the Services Stats view for any Core service:

- Summary Stats section
- Gauges section
- Timelines section
- Historical Timelines section
- Chart Stats Tray

Summary Stats Section

The Summary Stats section is at the top of the default view, and has no editable fields.

There are five panels in the Summary Stats section. The **Key Stats** panel displays different statistics for different types of services. The remaining panels in the Summary Stats section are the same for all types of services.

Key Stats

The Key Stats panel displays different statistics for different types of services.

- For a Decoder or Log Decoder, key statistics include capture statistics, such as capture rate, total packets or logs captured, total packets or logs dropped, the data capture begin time and end time.

Key Stats	
Capture Rate	0 MBPS
Max Capture Rate	33 MBPS
Total Captured	8.2 Million Packets
Total Dropped	0 Packets (0% loss)
Total Packets	271,941 Packets
Begin Time	2008-Feb-13 16:55:19
End Time	2015-Jan-23 05:15:47

- A Broker or Concentrator aggregates data from multiple services. Therefore, the key statistics for all aggregate services are presented in a grid. The columns in the grid provide the service name, the capture rate, the maximum capture rate, the number of session behind (that need to be aggregated), and the service status.

Key Stats				
Key Stats	Rate	Max	Behind	Status
	0	2346	0	consumir
	0	0	0	consumir
	0	26	0	consumir

Service System Info


The Service System Info panel includes the percentage of CPU used by the service, the memory usage statistics (system, total, process, and maximum process), service uptime, status, running since time, and the current time.

Service System Info	
CPU	7%
System Memory	14.9 GB
Total Memory	15.6 GB
Process Memory	111.4 MB
Max Process Memory	15.6 GB
Uptime	1 week, 6 days, 3 hours and 25 minutes
Status	Ready
Running Since	2015-Jan-23 09:29:11

Host System Info includes percentage of CPU used by the host, the memory usage statistics (system, total, process, and maximum), host uptime, status, running since time, and the current time.

Host System Info	
CPU	0%
System Memory	31.2 GB
Total Memory	31.4 GB
Process Memory	22.9 MB
Max Process Memory	31.4 GB
Uptime	5 weeks, 1 day, 19 hours and 57 minutes
Status	Ready

Logical Drives and **Physical Drives** are shown with an icon for the drive name and state. Drive types used in the names and the drive status options are listed below.



Drive Types and Status

Drive Type	Description	Comment	Status Options
sd	SCSI block device	Directly connected SAS, SATA MegaRAID volumes	OK (green) FAIL (red)
ld	MegaRAID Logical Volume	Defined in BIOS or with MegaCLI tool	OK (green) DEGRADED (yellow) BUILDING (yellow) FAIL (red)
pd	MegaRAID Physical Disks	Not directly exposed to Linux	OK (green) FAIL (red)
md	Linux software RAID Volume		OK (green) DEGRADED (yellow) BUILDING (yellow) FAIL (red)

Gauges

The Gauges section in the Stats View presents statistics in the form of analog gauges. See [Features](#) for details on configuring gauges.

Timelines

Timeline charts display the selected statistics in a running timeline with focus on the current time. This is the same for all types of services, and only the display name of the timeline is editable. See [Timeline Charts](#) for details on configuring timelines.

Historical Timelines

Historical timeline charts display statistics for session size, sessions, and packets in a historical timeline. This is the same for all types of services, and has an editable display name, begin date, and end date. See [Timeline Charts](#) for details on configuring timelines.

Note: Historical Timeline charts is being deprecated for Log Collector, Virtual Log Collector (VLC) and Windows Legacy Collector services.

Chart Stats Tray

The Chart Stats Tray lists all available statistics for the selected service type. Different services have different statistics to monitor. See [Components](#) for a detailed description.

Topics

- [Components](#)
- [Features](#)
- [Timeline Charts](#)

Chart Stats Tray

This topic describes the Chart Stats Tray in the Services Stats view.

In the Services Stats view, the Chart Stats Tray provides a way to customize the monitored statistics for individual services. The Chart Stats Tray lists all available statistics for the service. The number of statistics varies according to the type of service being monitored. Any statistic in the Chart Stats Tray can be displayed in a gauge or a timeline chart. Only statistics for session size, sessions, and packets are viewable in historical timeline charts.

To access the Services Stats view:

1. In the **NetWitness Platform** menu, select **ADMIN > Services**.


The Administration Services view is displayed.

2. Select a service and select  > **View > Stats**.

The Chart Stats Tray is on the right side.

3. If the tray is collapsed, click  to view the list of available statistics.

The following example shows the Services Stats view for a Decoder. The Chart Stats Tray is collapsed.



Components

The Chart Stats Tray has different statistics for different types of services. In the example above, 111 statistics are available for the Decoder. The following table describes features of the Chart Stat Tray.

Feature	Description
	Click to expand the panel horizontally.
	Click to collapse the panel horizontally.
Search	Type a search term in the field and press RETURN . Statistics that match are displayed with the matching word highlighted.
	Click to go to the first page.
	Click to go to the previous page.
	Type a page number in the Page field.
	Click to go to the next page.
	Click to go to the last page.
	Click to refresh the view.
s 1 - 12 of	Displays the range of statistics being displayed. The total number statistics varies by service type.

Gauges


This topic introduces the features of the Gauges section in the Services Stats view.

The Gauges section of the Services Stats view presents statistics in the form of an analog gauge. You can drag any statistic available in the Chart Stats Tray to the Gauges section. The properties of each individual gauge are editable; all gauges have an editable title and some have additional editable properties.

To access the Services Stats view:

1. In the **NetWitness Platform** menu, select **ADMIN > Services**
The Administration Services view is displayed.
2. Select a service and select  **> View > Stats**.
The Services Stats view includes the Gauges section.

The following figure shows the default gauges in the Services Stats view for a Log Decoder.



Features

The default gauges show these statistics:

- Process memory use
- CPU use
- Maximum process memory used

The controls in the Gauges title bar and in each gauge are the standard dashlet controls.


- In the Gauges title bar, you can collapse and expand the section and page forward or back.
- In each gauge, you can edit properties (⚙) and delete (X) the gauge.

Timeline Charts


This topic describes the features of the timeline charts in the Services Stats view.

Timeline charts display statistics in a running timeline. The Services Stats view includes two types of timelines: current time and historical. You can drag any statistic available in the Chart Stats Tray to the Timeline Charts section. Only statistics for session size, sessions, and packets are viewable in historical timeline charts. The properties of an individual timeline chart are editable; all timeline charts have an editable title and some have additional editable properties.

The following figure is an example of a current timeline showing the value and timestamp of a data point.



The following figure is an example of a historical timeline chart.



The default current timeline charts show these statistics:

- Memory Process
- CPU
- Memory Process Max

The historical time charts show these statistics:

- Sessions
- Packets
- Session Size

The controls in the Timeline Charts title bar and in each timeline are the standard dashlet controls.

- In the Timeline Charts title bar, you can collapse and expand the section and page forward or back.
- In each timeline, you can edit Properties (⚙) and delete (✕) the timeline.
- Hovering over a data point in the chart, displays the value and timestamp for the selected point.

System View

This topic introduces features in the System view using the Decoder and Log Decoder as an example. See the Configuration Guides individual services (for example for the *RSA NetWitness® Platform Broker and Concentrator Configuration Guide*) for details on their **ADMIN > Services > System Views**.

A Log Decoder is a special type of Decoder, and is configured and managed in a similar way to a Decoder. Therefore, most of the information in this section refers to both types of Decoders. Differences for Log Decoders are noted.


To access the Services System view for a Decoder:

1. In the **NetWitness Platform** menu, go to **ADMIN > Services**.

The Services view is displayed.

2. Select a service and select  > **View> System**.

The following figure shows an example of the Services System view for a Decoder.




The screenshot displays the RSA NetWitness Platform Admin console interface. The top navigation bar includes tabs for RESPOND, INVESTIGATE, MONITOR, CONFIGURE, and ADMIN. The ADMIN tab is active, and the left sidebar shows the path: Hosts > Services > E Broker > Health & Wellness > System > Security. The main content area is titled 'Change Service | Decoder | System' and contains several sections:

- Decoder Service Information:**
 - Name: Decoder
 - Version: 11.x.x.x (Rev Null)
 - Memory Usage: 3797 MB (2.95% of 126 GB)
 - CPU: 0%
 - Running Since: 2018-Jun-01 17:15:05
 - Uptime: 3 days 22 hours 45 minutes 37 seconds
 - Current Time: 2018-Jun-05 16:00:42
- Appliance Service Information:**
 - Name: Decoder (Host)
 - Version: 11.x.x.x (Rev Null)
 - Memory Usage: 26236 KB (0.02% of 126 GB)
 - CPU: 0%
 - Running Since: 2018-Jun-01 17:07:59
 - Uptime: 3 days 22 hours 52 minutes 44 seconds
 - Current Time: 2018-Jun-05 16:00:43
- Decoder User Information:**
 - Name: admin
 - Groups: Administrators
 - Roles: aggregate.manage, connections.manage, database.manage, decoder.manage, dpo.manage, index.manage, logs.manage, parsers.manage, rules.manage, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage
- Host User Information:**
 - Name: admin
 - Groups: Administrators
 - Roles: appliance.manage, connections.manage, logs.manage, services.manage, storedproc.execute, storedproc.manage, sys.manage, users.manage
- Session Information:**

Session	User	IP Address	Login Time ^	Active Queries
579	admin	IP address	2018-Jun-01 17:15:14	0


The following figure shows the Services System view for a Log Decoder.



Features

Services Info Toolbar

The following toolbars show the options specific to Log Decoders and Decoders.



In addition to the common options in the Services System view toolbar, you can start and stop capture of packets or logs. The upload file options are different for the standard Decoder (packet capture file) and the Log Decoder (log file).

Action	Description
Upload Packet Capture File	Displays a dialog that provides a way to select a packet capture (.pcap) file for upload to the selected Decoder. For more information, see the Upload Packet Capture File topic in the <i>Decoder and Log Decoder Configuration Guide</i> . Note: This option does not apply to Log Decoders.
Upload Log File	Displays a dialog that provides a way to select a log (.log) file for upload to the selected Log Decoder. For more information, see the Upload Log File to a Log Decoder topic in the <i>Decoder and Log Decoder Configuration Guide</i> .

Action	Description
Start/Stop Capture	Starts packet capture on the selected Decoder. When packet capture is in progress, the option in the toolbar changes to Stop Capture, and the option to upload a file is unavailable.

Host Task List Dialog

This topic introduces the Services System view > Host Task List dialog.

In the RSA NetWitness Platform Services System view, you can use the Host Tasks option to manage tasks that relate to a host and its communications with the network. Several service and host configuration options are available for Core services.

To access the Host Tasks dialog:


1. In **NetWitness Platform**, select **ADMIN > Services**.

2. Select a service and select  > **View> System**.

The System View for the service is displayed.

3. In the **Services System view** toolbar, click **Host Tasks**.

The Host Task List dialog is displayed. The **Task** list offers a list of supported messages for the associated host.

The image shows a screenshot of the 'Host Task List' dialog box. It has a dark gray title bar with the text 'Host Task List' and a close button (X) on the right. The main area is white and contains four labeled input fields: 'Task' (a dropdown menu), 'Arguments' (a text box), 'Info' (a text box), and 'Output' (a text box). To the right of the 'Arguments' field is a 'Run' button. At the bottom right of the dialog is a 'Cancel' button.

Features

The table below describes the dialog features.

Field	Description
Task	An entry field in which you type or select a message for a Core host. When you click in this field a drop-down list of available host tasks is displayed.

Field	Description
Arguments	An entry field in which you enter the arguments, if any, for the message.
Run	Executes the task and arguments in the entry fields.
Info	Information about the message purpose and syntax.
Output	The output or result of an executed task.
Cancel	Closes the Host Task list dialog.

Host Task Selection List

These tasks are displayed as a drop-down list in the Task field. The available options are regulated by the security role required to execute the option.

Task	Description
Add Filesystem Monitor	Starts monitoring the storage services attached to the specified filesystem (see Add and Delete a Filesystem Monitor).
Delete Filesystem Monitor	Stops monitoring the storage services attached to the specified filesystem.
Reboot Host	Shuts down and restarts the host (see Reboot a Host).
Set Host Built-in Clock	Sets the host local clock (see Set Host Built-In Clock).
Set Host Hostname	This method of changing the hostname is deprecated in NetWitness Platform 10.6; replaced by the procedure described in Hosts and Services Procedures
Set Network Configuration	Sets network address parameters (see Set Network Configuration).
Set Network Time Source	Sets the clock source for this host (see Set Network Time Source).
Set Syslog Forwarding	Enables or disables syslog forwarding from a remote server to the selected service (see Set Syslog Forwarding).
Show Network Port Status	Shows the network interface information for a host (see Show Network Port Status).
Show Serial Number	Gets the host serial number (see Show Serial Number).
Shut Down Host	Shuts down the physical host and the host <u>remains off</u> (see Shut Down Host).
Start Service	Starts a service on this host (see Start, Stop, or Restart a Service).

Task	Description
Stop Service	Stops a service on this host.
setSNMP	Enables or disables the SNMP service on a host (see Set SNMP).

Service Configuration Settings

This topic introduces the available service configuration settings for RSA NetWitness Platform Core services.

NetWitness Platform Core services include Brokers, Concentrators, Decoders, Log Decoders, Archivers, and the Appliance service. The service configuration parameters listed in these tables constitute all viewable and configurable parameters. Some parameters are configurable in various parts of the NetWitness Platform user interface and others are viewable or configurable only on the Services Explore view.

Appliance Service Configuration Parameters

This topic lists and describes the available the configuration parameters for the NetWitness Platform Core Appliance service.

The NetWitness Platform Core Appliance service provides hardware monitoring on legacy NetWitness hardware.

This table describes the Appliance Configuration parameters.


Appliance Parameter Field	Description
Logs	/logs/config, see Core Service Logging Configuration Parameters
REST	/rest/config, see REST Interface Configuration Parameters
Services	/services/<service name>/config, see Core Service-to-Service Configuration Parameters
System	/sys/config, see Core Service System Configuration Parameters

Archiver Service Configuration View

This topic lists and describes the available configuration settings for NetWitness Platform Archivers.

Workflow

The following workflow show the configuration tasks for the Archiver service.



Role	I want to ...
Administrator	Configure Meta Filters for Aggregation. Refer to "(Optional) Configure Meta Filters for Aggregation" in the <i>RSA NetWitness Platform Archiver Configuration Guide</i> for instructions.
Administrator	Configure Group Aggregation. Refer to "Configure Group Aggregation" in the <i>RSA NetWitness Platform Deployment Guide</i> for instructions.

Quick Look

To access the Services Config view:

- In **NetWitness Platform**, select **ADMIN > Services**.
The Admin Services view is displayed.
- Select an Archiver service and select  > **View > Config**.
Services Config view for the Archiver service is displayed.

This is an example of the Services Config view for an Archiver.

Broker Service Configuration Parameters

This topic lists and describes the configuration parameters for NetWitness Platform Brokers.

This table lists and describes the Broker configuration parameters.

Broker Parameter Field	Description
Broker	/broker/config refer to Aggregation Configuration Parameters
aggregate.interval.behind	Minimum number of milliseconds before another round of aggregation is requested when the broker is behind. Change takes effect immediately.
Database	/database/config refer to the Database Configuration Nodes topic in the <i>NetWitness Platform Core Services Database Tuning Guide</i>
Index	/index/config
index.dir	The directory where the broker device mapping files are stored. Change takes effect on service restart.
language.filename	The index language specification (XML) that is loaded on startup. Change requires service restart.
Logs	/logs/config refer to Core Service Logging Configuration Parameters
REST	/rest/config refer to REST Interface Configuration Parameters
SDK	/sdk/config refer to the SDK Configuration Nodes topic in the <i>NetWitness Platform Core Services Database Tuning Guide</i> and NetWitness Platform Core Service system.roles Modes
Services	/services/<service name>/config refer to Core Service-to-Service Configuration Parameters
System	/sys/config refer to Core Service System Configuration Parameters

Aggregation Configuration Parameters

This topic lists and describes the available configuration parameters that are common to services that perform aggregation, such as NetWitness Platform Concentrators and Archivers.

This table lists and describes the parameters that control aggregation on an aggregating service.

Configuration Path	/concentrator/config or /archiver/config
aggregate.autostart	Automatically restarts aggregation after a service restart, if enabled. Change takes effect immediately.
aggregate.buffer.size	Displays the size of the buffer (default unit is KB) used per round of aggregation. Larger buffers may improve aggregation performance but could impact query performance. Change takes effect after aggregation restart.
aggregate.crc	If enabled, all aggregation streams will be CRC validated. Change takes effect immediately.
aggregate.hours	Displays the maximum number of hours behind a service will be allowed to start aggregation. Change takes effect immediately.
aggregate.interval	Lists the minimum number of milliseconds before another round of aggregation is requested. Change takes effect immediately.
aggregate.meta.page.factor	Lists the allocated number meta pages per session used for aggregation. Change takes effect on service restart.
aggregate.meta.perpage	Lists the allocated number of meta stored on one page of data. Change takes effect on service restart.
aggregate.precache	Determines if the concentrator will precache the next round of aggregation for upstream services. Can improve aggregation performance but could impact query performance. Change takes effect immediately.
aggregate.sessions.max	Lists the number of sessions to aggregate on each round. Change takes effect after aggregation restart.
aggregate.sessions.perpage	Lists the number of sessions stored on one page of data. Change takes effect on service restart.
aggregate.time.window	Displays the maximum +/- time window, in seconds, that all services must be inside before another round of aggregation is requested. Zero turns off time window. Change takes effect immediately.
consume.mode	Determines if the concentrator can only aggregate locally or over a network, based on licensing restrictions. Change takes effect on service restart.
export.enabled	Allows export of session data, if enabled. Change takes effect on service restart.
export.expire.minutes	Lists the number of minutes before export cache files are expired and flushed. Change takes effect immediately.

Configuration Path	/concentrator/config or /archiver/config
export.format	Determines the file format used during data export. Change takes effect on service restart.
export.local.path	Displays the local location to cache exported data. Optional assigned max size (=#unit), units are: t for TB; g for GB, m for MB. Change takes effect on service restart.
export.meta.fields	Determines which meta fields are exported. Comma list of fields. Star means all fields. Star plus field list means all fields BUT listed fields. Just field list says just include those fields. Change takes effect immediately.
export.remote.path	Displays the remote protocol (nfs://) and location to export data. Change takes effect on service restart.
export.rollup	Determines the rollup interval for export files. Change takes effect on service restart.
export.session.max	Displays the maximum sessions per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.size.max	Displays the maximum bytes per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.usage.max	Displays the maximum percentage of cache space used before stopping aggregation. Zero is no limit. Change takes effect immediately.
heartbeat.error	Lists the number of seconds to wait after a service error before attempting a service reconnect. Change takes effect immediately.
heartbeat.interval	Lists the number of milliseconds between heartbeat service checks. Change takes effect immediately.
heartbeat.next.attempt	Lists the number of seconds to wait before attempting a service reconnect. Change takes effect immediately.
heartbeat.no.response	Lists the number of seconds to wait before taking unresponsive service offline. Change takes effect immediately.

Concentrator Service Configuration Parameters

This topic lists and describes the available configuration parameters for NetWitness Platform Concentrators.

This table lists and describes the Concentrator configuration parameters .

Concentrator Parameter Field	Description
Concentrator	/concentrator/config refer to Aggregation Configuration Parameters
Database	/database/config refer to the Database Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i>
Index	/index/config refer to the Index Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i>
Logs	/logs/config refer to Core Service Logging Configuration Parameters
REST	/rest/config refer to REST Interface Configuration Parameters
SDK	sdk/config refer to the SDK Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i> and NetWitness Platform Core Service system.roles Modes
Services	/services/<service name>/config refer to Core Service-to-Service Configuration Parameters
System	/sys/config refer to Core Service System Configuration Parameters

Core Service Logging Configuration Parameters

This topic lists and describes the logging configuration parameters for all NetWitness Platform Core services.

Logging configuration is the same on all NetWitness Platform Core services.

The following table describes the logging configuration parameters:

Logs Configuration Folder	/logs/config
log.dir	Displays the directory where the log database is stored. Optional assigned max size (= #) is in MBs. Change takes effect on service restart.
log.levels	Controls what types of log messages are stored (comma separated). Module specific settings are defined like this: <Module>=[debug info audit warning failure all none]. Change takes effect immediately.
log.snmp.agent	Sets a remote SNMP Trap Receiving agent.
snmp.trap.version	Sets the SNMP version to be used for gets and traps (2c or 3).
snmpv3.engine.boots	Displays the SNMPv3 engine boots count. This field auto-increments on startup and should not normally need to be set by the user.

Logs Configuration Folder	/logs/config
snmpv3.engine.id	Sets the SNMPv3 engine ID, which is 10-64 hexadecimal digit number optionally preceded by 0x. You can add suffix values at the end of the engine ID for each of the SA Core services running on the same host. For example, if the generated Engine ID for the SA Core host is 0x1234512345, you can set the Engine ID for the Decoder service as 0x123451234501 and set 0x123451234504 for the Appliance service.
snmpv3.trap.auth.local.key	Sets the SNMPv3 Trap Authentication Local Key, which is a 16 or 20 hexadecimal digit number (depending on which authentication protocol is used) preceded by 0x. For MD5, the key is 16 hexadecimal digits, while SHA uses 20 hexadecimal digits. You can use any desired algorithm to generate the local keys. It is recommended that a generation method involving randomness be used as opposed to selecting key values manually.
snmpv3.trap.auth.protocol	Displays the SNMPv3 Trap Authentication Protocol (none, MD5 or SHA).
snmpv3.trap.priv.local.key	Sets the SNMPv3 Trap Privacy Local Key, which is a 16 hexadecimal digit number preceded by 0x.
snmpv3.trap.priv.protocol	Displays the SNMPv3 Trap Privacy Protocol (none or AES).
snmpv3.trap.security.level	Displays the SNMPv3 Trap Security Level, which indicates whether authentication and privacy are used or not. Possible values are noAuthNoPriv, authNoPriv or authPriv.
snmpv3.trap.security.name	Sets the SNMPv3 Trap Security Name used during SNMPv3 trap authentication.
syslog.size.max	Displays the maximum size of a log sent to syslog (some syslog daemons have issues with very large messages). Zero means no limit. Change takes effect immediately.

Core Service-to-Service Configuration Parameters

This topic lists and describes the configuration parameters that control how a Core service connects to another Core service. For example, when a Concentrator connects to a decoder, the parameters of that connection are controlled by these settings.

Whenever a Core service establishes a connection to another Core service, the service that acts as the **client** creates a new sub-folder in the /services folder of the configuration tree. The name of the sub-folder corresponds to the name of the service and has the form `host:port`. For example, the service connection folder for a Concentrator connection to a Decoder could be `/services/reston-vadecoder:50004`. Inside each service connection folder, there is a `config` sub-folder that holds configurable parameters.

The following table describes the Service Configuration parameters:

Services	/services/host:port/config
----------	----------------------------

Services	/services/host:port/config
allow.nonssl.to.ssl	Allows a non-SSL connection to connect to a SSL service, when set to true. Otherwise, if false, non-secure to secure connections will be denied. Change takes effect immediately.
compression	Displays a config node that determines if data is compressed before sending. A positive value determines the number of bytes that need to be sent before it will be compressed. Zero means no compression.
crc.checksum	Displays a config node that determines if data streams are validated with a CRC checksum. A positive value determines the number of bytes that need to be sent before it will be CRC validated. Zero means no CRC validation.
ssl	Displays a config node that enables or disables SSL encryption on the connection.

Core Service System Configuration Parameters

This topic lists and describes the configuration parameters that are common to all NetWitness Platform Core services.

The following table lists and describes the System configuration parameters:

System Configuration Folder	/sys/config
compression	Displays the minimum amount of bytes before a message is compressed, when set to a positive value. Zero means no compression for any message. Change takes effect on subsequent connections.
crc.checksum	Displays the minimum bytes before a message is sent over the network with a CRC checksum (to be validated by the client), when set to a positive value. Zero means no CRC checksum validation with any message. Change takes effect on subsequent connections.
drives	Displays drives to monitor for usage stats. Change takes effect on service restart.
port	Displays the port this service will listen on. Change takes effect on service restart.
scheduler	Displays the folder for scheduled tasks.
service.name.override	Displays an optional service name used by upstream services for aggregation in lieu of hostname.
ssl	Encrypts all traffic using SSL, if enabled. Change takes effect on service restart.
stat.compression	Compresses stats as they are written to the database, if enabled. Change takes effect on service restart.

System Configuration Folder	/sys/config
stat.dir	Displays the directory where the historical stats database is stored (separate multiple dirs with semicolon). Optional assigned max size (=#unit), units are: t for TB; g for GB, m for MB. Change takes effect on service restart.
stat.exclude	Lists stat pathnames to be excluded from the stat database. The following wildcards are permitted: ? match any single character, * match zero or more characters to delimiter /, ** match zero or more characters including delimiter. Change takes effect immediately.
stat.interval	Determines how often (in milliseconds) statistic nodes are updated in the system. Change takes effect immediately.
threads	Lists the number of threads in the thread pool to handle incoming requests. Change takes effect immediately.

Decoder Service Configuration Parameters

This topic lists and describes the available configuration parameters for NetWitness Platform Decoders.

Decoder Parameter Field	Description
Decoder	/decoder/config refer to Decoder and Log Decoder Configuration Parameters
Database	/database/config refer to the Database Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i>
Index	/index/config refer to the Index Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i>
Logs	/logs/config refer to Core Service Logging Configuration Parameters
REST	/rest/config refer to REST Interface Configuration Parameters
SDK	/sdk/config refer to the SDK Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i> and NetWitness Platform Core Service system.roles Modes
System	/sys/config refer to Core Service System Configuration Parameters

Decoder and Log Decoder Configuration Parameters

This topic lists and describes the configuration parameters that are identical on both Decoder and Log Decoder services.

Configuration Path	<service>/config
aggregate.buffer.size	Displays the size of the buffer (default unit is KB) used per round of aggregation. Larger buffers may improve aggregation performance but could impact capture performance. Change takes effect after capture restart.
aggregate.precache	Determines if the decoder will pre-cache the next round of aggregation for upstream services. Can improve aggregation performance but could impact capture performance. Change takes effect immediately.
assembler.pool.ratio	Displays the percentage of pool pages that assembler manages and uses for the assembly process. Change takes effect on service restart.
assembler.session.flush	Flushes sessions when they are complete (1) or flushes sessions when they are parsed (2). Change takes effect on service restart.
assembler.session.pool	Lists the number of entries in the session pool. Change takes effect on service restart.
assembler.size.max	Lists the maximum size that a session will obtain. A setting of 0 removes the session size limit. Change takes effect immediately.
assembler.size.min	Lists the minimum size that a session must be before persisting. Change takes effect immediately.
assembler.timeout.packet	Lists the number of seconds before packets are timed out. Change takes effect immediately.
assembler.timeout.session	Lists the number of seconds before sessions are timed out. Change takes effect immediately.
assembler.voting.weights	Displays the weights used to determine which session stream is marked client and server. Change takes effect immediately.
capture.autostart	Determines if capture begins automatically when the service starts. Change takes effect on service restart.
capture.buffer.size	Displays capture memory buffer allocation size (default unit is MB). Change takes effect on service restart.

Configuration Path	<service>/config
capture.device.params	Displays capture service specific parameters. Change takes effect on service restart. The parameters understood by this field are specific to the currently selected capture device. If any of the parameters are not recognized by the current capture device, they are ignored. On Log Decoders, there is only the Log Events capture device. It accepts some optional parameters. • use-envision-time: If this is set to 1, the time meta for each event will be imported from the Log Collector stream. If this is 0 or not set, the imported event time will be stored in the event.time meta. • port: This parameter can be set to a numeric value to override the default syslog port listener, 514.
capture.selected	Displays current capture service and interface. Change takes effect immediately.
export.expire.minutes	Lists the number of minutes before export cache files are expired and flushed. Change takes effect immediately.
export.packet.enabled	Allows export of packet data, if enabled. Change takes effect on service restart.
export.packet.local.path	Displays the local location to cache packet exported data. Optional assigned max size (=#unit), units are: t for TB; g for GB, m for MB. Change takes effect on service restart.
export.packet.max	Displays the maximum packets per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.packet.remote.path	Lists the remote protocol (nfs://) and location to export data. Change takes effect on service restart.
export.packet.size.max	Displays the packet maximum bytes per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.rollup	Determines the rollup interval for export files. Change takes effect on service restart.
export.session.enabled	Allows export of session data, if enabled. Change takes effect on service restart.
export.session.format	Determines the file format used during session export. Change takes effect on service restart.
export.session.local.path	Displays the local location to cache session exported data. Optional assigned max size (=#unit), units are: t for TB; g for GB, m for MB. Change takes effect on service restart.

Configuration Path	<service>/config
export.session.max	Displays the maximum sessions per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.session.meta.fields	Determines which meta fields are exported. Comma list of fields. Star means all fields. Star plus field list means all fields BUT listed fields. Just field list says just include those fields. Change takes effect immediately.
export.session.remote.path	Displays the remote protocol (nfs://) and location to export data. Change takes effect on service restart.
export.session.size.max	Lists the session maximum bytes per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
export.usage.max	Lists the session maximum bytes per exported file. For export file types that cache this determines cached memory sizes. Zero is no limit. Change takes effect immediately.
parse.threads	Lists the number of parse threads to use for session parsing. Zero means let server decide. Change takes effect on service restart.
pool.packet.page.size	Displays the size of a packet page (default is KB). Change takes effect on service restart.
pool.packet.pages	Lists the number of packet pages decoder will allocate and use. Change takes effect on service restart.
pool.session.page.size	Displays the size of a session page (default is KB). Change takes effect on service restart.
pool.session.pages	Lists the number of session pages decoder will allocate and use. Change takes effect on service restart.

Log Decoder Service Configuration Parameters

This topic lists and describes the available configuration parameters for RSA NetWitness Platform Log Decoders.

Log Decoder Configuration Settings

This table lists and describes the Log Decoder configuration settings.

Log Decoder Setting Field	Description
Database	/database/config refer to the Database Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i> .
Decoder	/decoder/config refer to Decoder and Log Decoder Configuration Parameters

Log Decoder Setting Field	Description
Index	/index/config refer to the Index Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i> .
Logs	/logs/config refer to Core Service Logging Configuration.
REST	/rest/config refer to REST Interface Configuration
SDK	/sdk/config refer to the SDK Configuration Nodes topic in the <i>NetWitness Platform Core Database Tuning Guide</i> and Core Service system.role Modes.
System	/sys/config refer to Core Service System Configuration.

Log Tokenizer Configuration Settings

The log decoder has a set of configuration items that control how the automatic log tokenizer creates meta items from unparsed logs. The log tokenizer is implemented as a set of built-in parsers that each scan for a subset of recognizable tokens. The functionality of each of these native parsers is shown in the table below. These word items form a full-text index when they are fed to the indexing engine on the Concentrator and Archiver. By manipulating the parsers.disabled configuration entry, you can control which Log Tokenizers are enabled.

Parser Name	Description	Configuration Parameters
Log Tokens	Scans for runs of consecutive characters to produce 'word' meta items.	token.device.types, token.char.classes, token.max.length, token.min.length, token.unicode
IPSCAN	Scans for text that appears to be an IPv4 address to produce 'ip.addr' meta items.	token.device.types
IPV6SCAN	Scans for text that appears to be an IPv6 address to produce 'ipv6' meta items.	token.device.types
URLSCAN	Scans for text that appears to be a URI to produce 'alias.host', 'filename', 'username', and 'password' meta items.	token.device.types
DOMAINSCAN	Scans for text that appears to be a domain name to produce 'alias.host', 'tld', 'cctld', and 'sld' meta items.	token.device.types
EMAILSCAN	Scans for text that appears to be an email address to produce 'email' and 'username' meta items.	token.device.types

Parser Name	Description	Configuration Parameters
SYSLOGTIMESTAMPSCAN	Scans for text that appears to be syslog-format timestamps. Syslog is missing the year and time zone. When such text is located, it is normalized into UTC time to create 'event.time' meta items.	token.device.types
INTERNETTIMESTAMPSCAN	Scans for text that appears to be RFC 3339-format timestamps to create 'event.time' meta items.	token.device.types

These are the Log Tokenizer configuration parameters.

Log Decoder Parser Setting Field	Description
token.device.types	The set of device types that will be scanned for raw text tokens. By default, this is set to <code>unknown</code>, which means only logs that were not parsed will be scanned for raw text. You can add additional log types here to enrich parsed logs with text token information. If this field is empty, then log tokenization is disabled.
token.char.classes	This field controls the type of tokens that are generated. It can be any combination of the values <code>alpha</code>, <code>digit</code>, <code>space</code>, and <code>punct</code>. The default value is <code>alpha</code>. • alpha: Tokens may contain alphabetic characters • digit: Tokens may contain numbers • space: Tokens may contain spaces and tabs • punct: Tokens may contain punctuation marks
token.max.length	This field puts a limit on the length of the tokens. The default value is 5 characters. The maximum length setting allows the Log Decoder to limit the space needed to store the word metas. Using longer tokens requires more meta database space, but may provide slightly faster raw text searches. Using shorter tokens causes the text query resolver to have to perform more reads from the raw logs during searches, but it has the effect of using much less space in the metadb and index.
token.min.length	This is the minimum length of a searchable text token. The minimum token length will correspond to the minimum number of characters a user may type into the search box in order to locate results. The recommended value is the default, 3.

Log Decoder Parser Setting Field	Description
token.unicode	This boolean setting controls whether unicode classification rules are applied when classifying characters according to the token.char.classes setting. When this is set to true, each log is treated as a sequence of UTF-8 encoded code points and then classification is performed after the UTF-8 decoding is performed. When this is set to false, each log is treated as ASCII characters and only ASCII character classification is done. Unicode character classification requires more CPU resources on the Log Decoder. If you do not need non-English text indexing, you can disable this setting to reduce CPU utilization on the Log Decoder. The default is enabled.

REST Interface Configuration Parameters

This topic lists and describes the available configuration parameters for the REST interface built in to all NetWitness Platform Core Services.

Settings

The following table lists and describes the REST configuration parameters:

REST Configuration Path	/rest/config
cache.dir	Displays the host directory to use for temporarily creating and storing files. Change takes effect on service restart.
cache.size	Displays the total maximum size (default unit is MB) of all files in the cache directory before the oldest are deleted. Change takes effect on service restart.
enabled	Switches to enable or disable REST services, 1 is on, 0 is off. Change takes effect on service restart.
port	Displays the port the REST service will listen on. Change takes effect on service restart.
ssl	Encrypts all REST traffic using SSL, if enabled. The default 'system' means use setting from /sys/config/ssl. Change takes effect on service restart.

NetWitness Platform Core Service system.roles Modes

All NetWitness Platform Core services offer role-based authorization modes. This topic describes the modes that are available, and how they are configured within every service.

The configuration node `/sdk/config/system.roles` sets querying and viewing permissions for meta and content on a per key basis. This parameter supports the data privacy management function and when enabled using one of the non-zero values helps a data privacy officer to control access to specific meta keys and content. This parameter is configurable in the NetWitness Platform user interface (see the **Data Privacy Tab** topic in the *Data Privacy Management Guide* for details). When the value is edited, change takes effect immediately.

Zero means that service permissions based on SDK meta keys are disabled.

- 0 - disabled


When one of the non-zero values is specified, the data privacy officer can select a meta key to whitelist or blacklist the display of the associated meta, content, or both, for a specific user role on a service.

- 1 - whitelist meta and content filtered
- 2 - whitelist meta filtered
- 3 - whitelist content filtered
- 4 - blacklist meta and content filtered
- 5 - blacklist meta filtered
- 6 - blacklist content filtered

Troubleshooting Version Installations and Updates

This section describes the error messages displayed in the **Hosts** view when it encounters problems updating host versions and installing services on hosts in the **Hosts** view. If you cannot resolve an update or installation issue using the following troubleshooting solutions, contact Customer Support (<https://community.rsa.com/docs/DOC-1294>).

Update for Host fails

Error Message	
Problem	When you select an update version and click Update > Update Host, the download process is successful, but the update process fails.
Solution	1. Try to apply the version update to the host again. Often this is all you need to do. 2. If you still cannot apply the new version update, try the following: a. Monitor the following logs on NW Server as it progresses (for example, use submit the <code>tail -f</code> command string from the command line): <pre data-bbox="423 1423 1300 1612">/var/netwitness/uax/logs/sa.log /var/log/netwitness/orchestration-server/orchestration-server.log /var/log/netwitness/deployment-upgrade/chef-solo.log /var/log/netwitness/config-management/chef-solo.log /var/lib/netwitness/config-management/cache/chef-stacktrace.out</pre> The error will appear in one or more of these logs. b. Try to resolve the issue and reapply the version update. • Cause 1: <code>deploy_admin</code> password has expired. Solution: Reset your <code>deploy_admin</code> password. To reset your <code>deploy_admin</code> password, see the procedure described below in deploy_admin Password Expired


- Cause 2: The `deploy_admin` password was changed on NW Server host but not changed on non-NW Server hosts. In this case, on all non-NW Server hosts on 11.x, run the following command using the matching `deploy_admin` password from NW Server host:

```
/opt/rsa/saTools/bin/set-deploy-admin-password
```

3. If you still cannot apply the update, gather the logs from step 2 and contact Customer Support: <https://community.rsa.com/docs/DOC-1294>.

Update for Service Fails

Error Message



Problem

When you select a host and click **Install** the install service process fails.

Solution

1. **Try to install the service again.**
Often this is all you need to do.
2. If you still cannot install the service, try the following:
 - a. Monitor the following logs on NW Server as it progresses (for example, use submit the `tail -f` command string from the command line):


```
/var/netwitness/uax/logs/sa.log
/var/log/netwitness/orchestration-server/orchestration-server.log
/var/log/netwitness/deployment-upgrade/chef-solo.log
/var/log/netwitness/config-management/chef-solo.log
/var/lib/netwitness/config-management/cache/chef-stacktrace.out
```

The error will appear in one or more of these logs.
 - b. Try to resolve the issue and reapply the service.
 - Cause 1: Entered the wrong `deploy_admin` password in `nwsetup-tui`.
Solution: Retrieve your `deploy_admin` password.


To retrieve your `deploy_admin` password:

1. In the NetWitness Platform menu, select **ADMIN > Security > Users** tab.
2. Select the `deploy_admin` and click **Reset Password**.
3. (Conditional) If NetWitness Platform does not allow you to reset expired `deploy_admin` password in the **Reset Password** dialog, complete the following steps.
 - a. SSH to the NW Server host.


```
security-cli-client --get-config-prop --prop-hierarchy
nw.security-client --prop-name
platform.deployment.password -quiet
```
 - b. SSH to the host that failed installation/orchestration.
 - c. Run the `nwsetup-tui` again using correct `deploy_admin` password.
- Cause 2: `deploy_admin` password has expired.

Solution: Reset your `deploy_admin` password. To reset your `deploy_admin` password, see the procedure described below in [deploy admin Password Expired](#)
3. If you still cannot apply the update, gather the logs from step 2 and contact Customer Support: <https://community.rsa.com/docs/DOC-1294>.


Update for Host Download Error

Error Message	
Problem	When you select an update version and click Update > Update Host , the download starts but fails to complete.
Cause	Version download files can be large and take a long time to download. If there are communication issues during the download it will fail.
Solution	1. Try to download it again. 2. If the download still fails, try to download it outside of NetWitness Platform as

described in [Apply Updates from the Command Line \(No Web Access\)](#).

3. If you still cannot download the update file, contact Customer Support: <https://community.rsa.com/docs/DOC-1294>.

deploy_admin Password Expired

Error Message	
Cause	The <code>deploy_admin</code> user password has expired.
Solution	Reset your <code>deploy_admin</code> password. 1. In the NetWitness Platform menu, select ADMIN > Security > Users tab. 2. Select the deploy_admin and click Reset Password. • If NetWitness Platform allows you to enter the expired <code>deploy_admin</code> password in the Reset Password dialog, complete the following steps. a. Enter the expired <code>deploy_admin</code> password. b. Uncheck the Force password change on next login checkbox. c. Click Save • If NetWitness Platform does not allow you to enter the expired <code>deploy_admin</code> password in the Reset Password dialog. a. On the NW Server host and all other hosts on 11.x , run the following command using the new <code>deploy_admin</code> password: <pre>/opt/rsa/saTools/bin/set-deploy-admin-password</pre> b. On the host that failed installation/orchestration, run the <code>nwsetup-tui</code> and use the new <code>deploy_admin</code> password.

