

# NetWitness<sup>®</sup> Platform

## Cisco Firepower System Event Streamer (eStreamer) Event Source Log Configuration Guide

# Cisco Firepower System Event Streamer (eStreamer)

## Event Source Product Information:

**Vendor:** [Cisco](#)

**Event Source:** FirePower System Event Streamer

**Versions:** 6.x, 7.x

## NetWitness Product Information:

**Supported On:** NetWitness Suite 12.3 and later

**Event Source Log Parser:** cef

**Collection Method:** Syslog

**Event Source Class.Subclass:** Security.Access Control

## Contact Information

NetWitness Community at <https://community.netwitness.com> contains a knowledge base that answers common questions and provides solutions to known problems, product documentation, community discussions, and case management.

## Trademarks

RSA and other trademarks are trademarks of RSA Security LLC or its affiliates ("RSA"). For a list of RSA trademarks, go to <https://www.rsa.com/en-us/company/rsa-trademarks>. Other trademarks are trademarks of their respective owners.

## License Agreement

This software and the associated documentation are proprietary and confidential to RSA Security LLC or its affiliates and are furnished under license, and may be used and copied only in accordance with the terms of such license and with the inclusion of the copyright notice below. This software and the documentation, and any copies thereof, may not be provided or otherwise made available to any other person.

No title to or ownership of the software or documentation or any intellectual property rights thereto is hereby transferred. Any unauthorized use or reproduction of this software and the documentation may be subject to civil and/or criminal liability.

This software is subject to change without notice and should not be construed as a commitment by RSA.

## Third-Party Licenses

This product may include software developed by parties other than RSA. The text of the license agreements applicable to third-party software in this product may be viewed on the product documentation page on NetWitness Community. By using this product, a user of this product agrees to be fully bound by terms of the license agreements.

## Note on Encryption Technologies

This product may contain encryption technology. Many countries prohibit or restrict the use, import, or export of encryption technologies, and current use, import, and export regulations should be followed when using, importing or exporting this product.

## Distribution

Use, copying, and distribution of any RSA Security LLC or its affiliates ("RSA") software described in this publication requires an applicable software license.

RSA believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

THE INFORMATION IN THIS PUBLICATION IS PROVIDED "AS IS." RSA MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WITH RESPECT TO THE INFORMATION IN THIS PUBLICATION, AND SPECIFICALLY DISCLAIMS IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

## Miscellaneous

This product, this software, the associated documentations as well as the contents are subject to NetWitness' standard Terms and Conditions in effect as of the issuance date of this documentation and which can be found at <https://www.netwitness.com/standard-form-agreements/>.

© 2024 RSA Security LLC or its affiliates. All Rights Reserved.

February, 2024

# Contents

---

<b>Configure eStreamer on Cisco FirePower</b> .....	<b>6</b>
<b>Configure RSA NetWitness Suite</b> .....	<b>7</b>
Ensure the Required Parser is Enabled .....	7
Configuring Syslog Collection .....	7
<b>Getting Help with NetWitness Platform</b> .....	<b>9</b>
Self-Help Resources .....	9
Contact NetWitness Support .....	9
Feedback on Product Documentation .....	10

To configure the Cisco FirePower System Event Streamer, you must:

- I. Configure eStreamer on Cisco FirePower System Event Streamer
- II. Configure RSA NetWitness Suite for Syslog Collection

## Configure eStreamer on Cisco FirePower

---

The Firepower System Event Streamer (eStreamer) eNcore CLI client uses a message-oriented protocol to stream events and host profile information to your client application from eStreamer server (Cisco FMC). Your client can request event and host profile data from a Management Center, and intrusion event data only from a managed device. Your client application initiates the data stream by submitting request messages, which specify the data to be sent, and then controls the message flow from the Management Center or managed device after streaming begins. Please follow the official document provided by Cisco to configure the eStreamer

<https://www.cisco.com/c/en/us/support/docs/security/firepower-ngfw/215631-understand-estreamer-and-troubleshoot-en.html>

**Note:** It is recommended that we should not run the external Cisco Python or shell script inside NetWitness components like logcollector or logdecoder. Please run those scripts inside a separate VM/server from the customer environment.

**Note:** Service port should be 514 and use the logcollector/logdecoder IP to send events from eStreamer to NetWitness. Please select adaptor in estreamer.conf as cef.

## Configure RSA NetWitness Suite

---

Perform the following steps in RSA NetWitness Suite:

- Ensure the required parser is enabled
- Configure Syslog Collection

### Ensure the Required Parser is Enabled

If you do not see your parser in the list while performing this procedure, you need to download it in RSA NetWitness Suite Live.

**Ensure that the parser for your event source is enabled:**



1. In the **NetWitness** menu, select **Administration > Services**.
2. In the Services grid, select a Log Decoder, and from the Actions menu, choose **View > Config**.
3. In the Service Parsers Configuration panel, search for your event source, and ensure that the **Config Value** field for your event source is selected.

**Note:** The required parser is **cef**.

### Configuring Syslog Collection

**Note:** You only need to configure Syslog collection the first time that you set up an event source that uses Syslog to send its output to NetWitness.

**To configure the Log Decoder for Syslog collection:**

1. In the NetWitness menu, select **Administration > Services**.
2. In the Services grid, select a Log Decoder, and from the Actions menu, choose **View > System**.
3. Depending on the icon you see, do one of the following
  - If you see  **Start Capture**, click the icon to start capturing Syslog.
  - If you see  **Stop Capture**, this Log Decoder is already capturing Syslog.

**To configure the Remote Log Collector for Syslog collection:**

1. In the **NetWitness** menu, select **Administration > Services**.
2. In the Services grid, select a Remote Log Collector, and from the Actions menu, choose **View > Config > Event Sources**.
3. Select **Syslog/Config** from the drop-down menu. The Event Categories panel displays the Syslog event sources that are configured, if any.
4. In the Event Categories panel toolbar, click **+**. The Available Event Source Types dialog is displayed.
5. Select either **syslog-tcp** or **syslog-udp**. You can set up either or both, depending on the needs of your organization.
6. Select the new type in the Event Categories panel and click **+** in the Sources panel toolbar. The Add Source dialog is displayed.
7. Enter **514** for the port, and select **Enabled**. Optionally, configure any of the Advanced parameters as necessary.

Click **OK** to accept your changes and close the dialog box.

Once you configure one or both syslog types, the Log Decoder or Remote Log Collector collects those types of messages from all available event sources. You can continue to add Syslog event sources to your system without any further configuration in NetWitness.

## Getting Help with NetWitness Platform

### Self-Help Resources

There are several options that provide you with help as you need it for installing and using NetWitness:

- See the documentation for all aspects of NetWitness here: <https://community.netwitness.com/t5/netwitness-platform/ct-p/netwitness-documentation>.
- Use the **Search** and **Create a Post** fields in NetWitness Community portal to find specific information here: <https://community.netwitness.com/t5/netwitness-discussions/bd-p/netwitness-discussions>.
- See the NetWitness Knowledge Base: <https://community.netwitness.com/t5/netwitness-knowledge-base/tkb-p/netwitness-knowledge-base>.
- See the documentation for Logstash JDBC input plugin here: <https://www.elastic.co/guide/en/logstash/current/plugins-inputs-jdbc.html>.
- See Troubleshooting section in the guides.
- See also [NetWitness® Platform Blog Posts](#).
- If you need further assistance, [Contact NetWitness Support](#).

### Contact NetWitness Support

When you contact NetWitness Support, please provide the following information:

- The version number of the NetWitness Platform or application you are using.
- Logs information, even source version, and collection method.
- If you have problem with an event source, enable **Debug** parameter (set this parameter to **On** or **Verbose**) and collect the debug logs to share with the NetWitness Support team.

Use the following contact information if you have any questions or need assistance.

NetWitness Community Portal	<a href="https://community.netwitness.com">https://community.netwitness.com</a> In the main menu, click <b>Support &gt; Case Portal &gt; View My Cases</b> .
International Contacts (How to Contact NetWitness Support)	<a href="https://community.netwitness.com/t5/support/ct-p/support">https://community.netwitness.com/t5/support/ct-p/support</a>
Community	<a href="https://community.netwitness.com/t5/netwitness-discussions/bd-p/netwitness-discussions">https://community.netwitness.com/t5/netwitness-discussions/bd-p/netwitness-discussions</a>

## Feedback on Product Documentation

You can send an email to [feedbacknwdocs@netwitness.com](mailto:feedbacknwdocs@netwitness.com) to provide feedback on NetWitness Platform documentation.